
labgrid Documentation

Release 0.3.4

Jan Luebbe, Rouven Czerwinski

May 14, 2021

CONTENTS

1	Getting Started	3
1.1	Installation	3
1.2	Running Your First Test	4
1.3	Setting Up the Distributed Infrastructure	5
1.4	udev Matching	8
1.5	Using a Strategy	8
2	Overview	11
2.1	Architecture	11
2.2	Remote Resources and Places	13
3	Usage	17
3.1	Remote Access	17
3.2	Library	19
3.3	pytest Plugin	21
3.4	Command-Line	27
4	Manual Pages	29
4.1	labgrid-client	29
4.2	labgrid-device-config	33
4.3	labgrid-exporter	35
5	Configuration	39
5.1	Resources	39
5.2	Drivers	53
5.3	Strategies	69
5.4	Reporters	71
5.5	Environment Configuration	72
5.6	Exporter Configuration	73
6	Development	77
6.1	Installation	77
6.2	Writing a Driver	77
6.3	Writing a Resource	79
6.4	Writing a Strategy	80
6.5	Tips for Writing and Debugging Tests	81
6.6	Graph Strategies	82
6.7	SSHManager	86
6.8	ManagedFile	87
6.9	ProxyManager	87
6.10	Contributing	87

6.11	Ideas	89
7	Design Decisions	91
7.1	Out of Scope	91
7.2	In Scope	91
7.3	Further Goals	92
8	Changes	93
8.1	Release 0.3.4 (released Apr 1, 2021)	93
8.2	Bug Fixes in 0.3.4	93
8.3	Release 0.3.3 (released Apr 1, 2021)	93
8.4	Bug Fixes in 0.3.3	93
8.5	Release 0.3.2 (released Mar 14, 2021)	93
8.6	Bug Fixes in 0.3.2	93
8.7	Release 0.3.1 (released Feb 5, 2021)	94
8.8	Bug Fixes in 0.3.1	94
8.9	Release 0.3.0 (released Jan 22, 2021)	94
8.10	Release 0.2.0 (released Jan 4, 2019)	96
8.11	Release 0.1.0 (released May 11, 2017)	100
9	Modules	101
9.1	labgrid package	101
10	Indices and Tables	203
	Python Module Index	205
	Index	207

labgrid is a embedded board control python library with a focus on testing, development and general automation. It includes a remote control layer to control boards connected to other hosts.

The idea behind labgrid is to create an abstraction of the hardware control layer needed for testing of embedded systems, automatic software installation and automation during development. labgrid itself is *not* a testing framework, but is intended to be combined with [pytest](#) (and additional pytest plugins). Please see [Design Decisions](#) for more background information.

It currently supports:

- pytest plugin to write tests for embedded systems connecting serial console or SSH
- remote client-exporter-coordinator infrastructure to make boards available from different computers on a network
- power/reset management via drivers for power switches or onewire PIOs
- upload of binaries via USB: imxusbloader/mxsusbloader (bootloader) or fastboot (kernel)
- functions to control external services such as emulated USB-Sticks and the [hawkBit](#) deployment service

While labgrid is currently used for daily development on embedded boards and for automated testing, several planned features are not yet implemented and the APIs may be changed as more use-cases appear. We appreciate code contributions and feedback on using labgrid on other environments (see [Contributing](#) for details). Please consider contacting us (via a GitHub issue) before starting larger changes, so we can discuss design trade-offs early and avoid redundant work. You can also look at [Ideas](#) for enhancements which are not yet implemented.

GETTING STARTED

This section of the manual contains introductory tutorials for installing labgrid, running your first test and setting up the distributed infrastructure. For an overview about the basic design and components of *labgrid*, read the [Overview](#) first.

1.1 Installation

Depending on your distribution you need some dependencies. On Debian stretch and buster these usually are:

```
$ apt-get install python3 python3-virtualenv python3-pip python3-setuptools virtualenv
```

In many cases, the easiest way is to install labgrid into a virtualenv:

```
$ virtualenv -p python3 labgrid-venv
$ source labgrid-venv/bin/activate
```

Start installing labgrid by cloning the repository and installing the requirements from the *requirements.txt* file:

```
$ git clone https://github.com/labgrid-project/labgrid
$ cd labgrid && pip install -r requirements.txt
$ python3 setup.py install
```

Note: Previous documentation recommended the installation as via pip (*pip3 install labgrid*). This lead to broken installations due to unexpected incompatibilities with new releases of the dependencies. Consequently we now recommend using pinned versions from the *requirements.txt* file for most use cases.

labgrid also supports the installation as a library via pip, but we only test against library versions specified in the *requirements.txt* file. Thus when installing directly from pip you have to test compatibility yourself.

Note: If you are installing via pip and intend to use Serial over IP (RFC2217), it is highly recommended to uninstall pyserial after installation and replace it with the pyserial version from the labgrid project:

```
$ pip uninstall pyserial
$ pip install https://github.com/labgrid-project/pyserial/archive/v3.4.0.1.
↪zip#egg=pyserial
```

This pyserial version has two fixes for an Issue we found with Serial over IP multiplexers. Additionally it reduces the Serial over IP traffic considerably since the port is not reconfigured when labgrid changes the timeout (which is done inside the library a lot).

Test your installation by running:

```
$ labgrid-client --help
usage: labgrid-client [-h] [-x URL] [-c CONFIG] [-p PLACE] [-d] COMMAND ...
...
```

If the help for `labgrid-client` does not show up, open an [Issue](#). If everything was successful so far, proceed to the next section:

1.1.1 Optional Requirements

labgrid provides optional features which are not included in the default *requirements.txt*. The tested library version for each feature is included in a separate requirements file. An example for snmp support is:

```
$ pip install -r snmp-requirements.txt
```

Onewire

Onewire support requires the *libow* library with headers, installable on debian via the *libow-dev* package. Use the *onewire-requirements.txt* file to install the correct onewire library version in addition to the normal installation.

SNMP

SNMP support requires to additional packages, *pysnmp* and *pysnmpmibs*. They are included in the *snmp-requirements.txt* file.

Modbus

Modbus support requires an additional package *pyModbusTCP*. It is included in the *modbus-requirements.txt* file.

1.2 Running Your First Test

Start by copying the initial example:

```
$ mkdir ../first_test/
$ cp examples/shell/* ../first_test/
$ cd ../first_test/
```

Connect your embedded board (raspberry pi, riotboard, ...) to your computer and adjust the `port` parameter of the `RawSerialPort` resource and `username` and `password` of the `ShellDriver` driver in `local.yaml`:

```
targets:
  main:
    resources:
      RawSerialPort:
        port: "/dev/ttyUSB0"
    drivers:
      ManualPowerDriver:
        name: "example"
      SerialDriver: {}
```

(continues on next page)

(continued from previous page)

```
ShellDriver:
  prompt: 'root@\w+: [^ ]+ '
  login_prompt: ' login: '
  username: 'root'
```

You can check which device name gets assigned to your USB-Serial converter by unplugging the converter, running `dmesg -w` and plugging it back in. Boot up your board (manually) and run your first test:

```
$ pytest --lg-env local.yaml test_shell.py
```

It should return successfully, in case it does not, open an [Issue](#).

If you want to build documentation you need some more dependencies:

```
$ pip3 install -r doc-requirements.txt
```

The documentation is inside `doc/`. HTML-Documentation is build using:

```
$ cd doc/
$ make html
```

The HTML documentation is written to `doc/.build/html/`.

1.3 Setting Up the Distributed Infrastructure

The labgrid *distributed infrastructure* consists of three components:

1. *Coordinator*
2. *Exporter*
3. *Client*

The system needs at least one coordinator and exporter, these can run on the same machine. The client is used to access functionality provided by an exporter. Over the course of this tutorial we will set up a coordinator and exporter, and learn how to access the exporter via the client.

1.3.1 Coordinator

To start the coordinator, we will download the labgrid repository, create an extra virtualenv and install the dependencies via the requirements file.

```
$ git clone https://github.com/labgrid-project/labgrid
$ cd labgrid && virtualenv -p python3 crossbar_venv
$ source crossbar_venv/bin/activate
$ sudo apt install libsnappy-dev
$ pip install -r crossbar-requirements.txt
$ python setup.py install
```

All necessary dependencies should be installed now, we can start the coordinator by running `crossbar start` inside of the repository.

Note: This is possible because the labgrid repository contains the crossbar configuration the coordinator in the `.crossbar` folder. crossbar is a network messaging framework for building distributed applications, which labgrid plugs into.

Note: For long running deployments, you should copy and customize the `.crossbar/config.yaml` file for your use case. This includes setting a different `workdir` and may include changing the running port.

1.3.2 Exporter

The exporter needs a configuration file written in YAML syntax, listing the resources to be exported from the local machine. The config file contains one or more named resource groups. Each group contains one or more resource declarations and optionally a location string (see the [configuration reference](#) for details).

For example, to export a `USBSerialPort` with `ID_SERIAL_SHORT` of `ID23421JLK`, the group name *example-group* and the location *example-location*:

```
example-group:
  location: example-location
  USBSerialPort:
    ID_SERIAL_SHORT: ID23421JLK
```

Note: Use `labgrid-suggest` to generate the YAML snippets for most exportable resources.

The exporter can now be started by running:

```
$ labgrid-exporter configuration.yaml
```

Additional groups and resources can be added:

```
example-group:
  location: example-location
  USBSerialPort:
    match:
      'ID_SERIAL_SHORT': 'P-00-00682'
    speed: 115200
  NetworkPowerPort:
    model: netio
    host: netiol
    index: 3
example-group-2:
  USBSerialPort:
    ID_SERIAL_SHORT: KSLAH2341J
```

Restart the exporter to activate the new configuration.

Attention: The *ManagedFile* will create temporary uploads in the exporters `/var/cache/labgrid` directory. This directory needs to be created manually and should allow write access for users. The `/contrib` directory in the labgrid-project contains a `tmpfiles` configuration example to automatically create and clean the directory. It is also highly recommended to enable `fs.protected_regular=1` and `fs.protected_fifos=1` for

kernels>=4.19, to protect the users from opening files not owned by them in world writeable sticky directories. For more information see [this kernel commit](#).

1.3.3 Client

Finally we can test the client functionality, run:

```
$ labgrid-client resources
kiwi/example-group/NetworkPowerPort
kiwi/example-group/NetworkSerialPort
kiwi/example-group-2/NetworkSerialPort
```

You can see the available resources listed by the coordinator. The groups *example-group* and *example-group-2* should be available there.

To show more details on the exported resources, use `-v` (or `-vv`):

```
$ labgrid-client -v resources
Exporter 'kiwi':
  Group 'example-group' (kiwi/example-group/*):
    Resource 'NetworkPowerPort' (kiwi/example-group/NetworkPowerPort[/
↳NetworkPowerPort]):
      {'acquired': None,
       'avail': True,
       'cls': 'NetworkPowerPort',
       'params': {'host': 'netio1', 'index': 3, 'model': 'netio'}}
  ...
```

You can now add a place with:

```
$ labgrid-client --place example-place create
```

And add resources to this place (`-p` is short for `--place`):

```
$ labgrid-client -p example-place add-match */example-group/*
```

Which adds the previously defined resource from the exporter to the place. To interact with this place, it needs to be acquired first, this is done by

```
$ labgrid-client -p example-place acquire
```

Now we can connect to the serial console:

```
$ labgrid-client -p example-place console
```

Note: Using remote connection requires `microcom` installed on the host where the `labgrid-client` is called.

See [Remote Access](#) for some more advanced features. For a complete reference have a look at the [labgrid-client\(1\)](#) man page.

1.4 udev Matching

labgrid allows the exporter (or the client-side environment) to match resources via udev rules. The udev resources become available to the test/exporter as soon as they are plugged into the computer, e.g. allowing an exporter to export all USB ports on a specific hub and making a `NetworkSerialPort` available as soon as it is plugged into one of the hub's ports. labgrid also provides a small utility called `labgrid-suggest` which will output the proper YAML formatted snippets for you. The information udev has on a device can be viewed by executing:

```
$ udevadm info /dev/ttyUSB0
...
E: ID_MODEL_FROM_DATABASE=CP210x UART Bridge / myAVR mySmartUSB light
E: ID_MODEL_ID=ea60
E: ID_PATH=pci-0000:00:14.0-usb-0:5:1.0
E: ID_PATH_TAG=pci-0000_00_14_0-usb-0_5_1_0
E: ID_REVISION=0100
E: ID_SERIAL=Silicon_Labs_CP2102_USB_to_UART_Bridge_Controller_P-00-00682
E: ID_SERIAL_SHORT=P-00-00682
E: ID_TYPE=generic
...
```

In this case the device has an `ID_SERIAL_SHORT` key with a unique ID embedded in the USB-serial converter. The resource match configuration for this USB serial converter is:

```
USBSerialPort:
  match:
    'ID_SERIAL_SHORT': 'P-00-00682'
```

This section can now be added under the resource key in an environment configuration or under its own entry in an exporter configuration file.

As the USB bus number can change depending on the kernel driver initialization order, it is better to use the `@ID_PATH` instead of `@sys_name` for USB devices. In the default udev configuration, the path is not available for all USB devices, but that can be changed by creating a udev rules file:

```
SUBSYSTEMS=="usb", IMPORT{builtin}="path_id"
```

1.5 Using a Strategy

Strategies allow the labgrid library to automatically bring the board into a defined state, e.g. boot through the boot-loader into the Linux kernel and log in to a shell. They have a few requirements:

- A driver implementing the `PowerProtocol`, if no controllable infrastructure is available a `ManualPowerDriver` can be used.
- A driver implementing the `LinuxBootProtocol`, usually a specific driver for the board's bootloader
- A driver implementing the `CommandProtocol`, usually a `ShellDriver` with a `SerialDriver` below it.

labgrid ships with two builtin strategies, `BareboxStrategy` and `UBootStrategy`. These can be used as a reference example for simple strategies, more complex tests usually require the implementation of your own strategies.

To use a strategy, add it and its dependencies to your configuration YAML, retrieve it in your test and call the `transition(status)` function.

```
>>> strategy = target.get_driver(strategy)
>>> strategy.transition("barebox")
```

An example using the pytest plugin is provided under *examples/strategy*.

OVERVIEW

2.1 Architecture

labgrid can be used in several ways:

- on the command line to control individual embedded systems during development (“board farm”)
- via a pytest plugin to automate testing of embedded systems
- as a python library in other programs

In the labgrid library, a controllable embedded system is represented as a *Target*. *Targets* normally have several *Resource* and *Driver* objects, which are used to store the board-specific information and to implement actions on different abstraction levels. For cases where a board needs to be transitioned to specific states (such as *off*, *in bootloader*, *in Linux shell*), a *Strategy* (a special kind of *Driver*) can be added to the *Target*.

While labgrid comes with implementations for some resources, drivers and strategies, custom implementations for these can be registered at runtime. It is expected that for complex use-cases, the user would implement and register a custom *Strategy* and possibly some higher-level *Drivers*.

2.1.1 Resources

Resources are passive and only store the information to access the corresponding part of the *Target*. Typical examples of resources are *RawSerialPort*, *NetworkPowerPort* and *AndroidFastboot*.

An important type of *Resources* are *ManagedResources*. While normal *Resources* are always considered available for use and have fixed properties (such as the `/dev/ttyUSB0` device name for a *RawSerialPort*), the *ManagedResources* are used to represent interfaces which are discoverable in some way. They can appear/disappear at runtime and have different properties each time they are discovered. The most common examples of *ManagedResources* are the various USB resources discovered using udev, such as *USBSerialPort*, *IMXUSBLoader* or *AndroidFastboot*.

2.1.2 Drivers and Protocols

A labgrid *Driver* uses one (or more) *Resources* and/or other, lower-level *Drivers* to perform a set of actions on a *Target*. For example, the *NetworkPowerDriver* uses a *NetworkPowerPort* resource to control the *Target*’s power supply. In this case, the actions are “on”, “off”, “cycle” and “get”.

As another example, the *ShellDriver* uses any driver implementing the *ConsoleProtocol* (such as a *SerialDriver*, see below). The *ConsoleProtocol* allows the *ShellDriver* to work with any specific method of accessing the board’s console (locally via USB, over the network using a console server or even an external program). At the *ConsoleProtocol* level, characters are sent to and received from the target, but they are not yet interpreted as specific commands or their output.

The *ShellDriver* implements the higher-level *CommandProtocol*, providing actions such as “run” or “run_check”. Internally, it interacts with the Linux shell on the target board. For example, it:

- waits for the login prompt
- enters user name and password
- runs the requested shell command (delimited by marker strings)
- parses the output
- retrieves the exit status

Other drivers, such as the *SSHDriver*, also implement the *CommandProtocol*. This way, higher-level code (such as a test suite), can be independent of the concrete control method on a given board.

2.1.3 Binding and Activation

When a *Target* is configured, each driver is “bound” to the resources (or other drivers) required by it. Each *Driver* class has a “bindings” attribute, which declares which *Resources* or *Protocols* it needs and under which name they should be available to the *Driver* instance. The binding resolution is handled by the *Target* during the initial configuration and results in a directed, acyclic graph of resources and drivers. During the lifetime of a *Target*, the bindings are considered static.

In most non-trivial target configurations, some drivers are mutually exclusive. For example, a *Target* may have both a *ShellDriver* and a *BareboxDriver*. Both bind to a driver implementing the *ConsoleProtocol* and provide the *CommandProtocol*. Obviously, the board cannot be in the bootloader and in Linux at the same time, which is represented in labgrid via the *BindingState* (*boundinactive*). If, during activation of a driver, any other driver in its bindings is not active, they will be activated as well.

Activating and deactivating *Drivers* is also used to handle *ManagedResources* becoming available/unavailable at run-time. If some resources bound to by the activating drivers are currently unavailable, the *Target* will wait for them to appear (with a per resource timeout). A realistic sequence of activation might look like this:

- enable power (*PowerProtocol.on*)
- activate the *IMXUSBDriver* driver on the target (this will wait for the *IMXUSBLoader* resource to be available)
- load the bootloader (*BootstrapProtocol.load*)
- activate the *AndroidFastbootDriver* driver on the target (this will wait for the *AndroidFastboot* resource to be available)
- boot the kernel (*AndroidFastbootDriver.boot*)
- activate the *ShellDriver* driver on the target (this will wait for the *USBSerialPort* resource to be available and log in)

Any *ManagedResources* which become unavailable at runtime will automatically deactivate the dependent drivers.

2.1.4 Multiple Drivers and Names

Each driver and resource can have an optional name. This parameter is required for all manual creations of drivers and resources. To manually bind to a specific driver set a binding mapping before creating the driver:

```
>>> t = Target("Test")
>>> SerialPort(t, "First")
SerialPort(target=Target(name='Test', env=None), name='First', state=<BindingState.
↳bound: 1>, avail=True, port=None, speed=115200)
```

(continues on next page)

(continued from previous page)

```
>>> SerialPort(t, "Second")
SerialPort(target=Target(name='Test', env=None), name='Second', state=<BindingState.
↳bound: 1>, avail=True, port=None, speed=115200)
>>> t.set_binding_map({"port": "Second"})
>>> sd = SerialDriver(t, "Driver")
>>> sd
SerialDriver(target=Target(name='Test', env=None), name='Driver', state=<BindingState.
↳bound: 1>, txdelay=0.0)
>>> sd.port
SerialPort(target=Target(name='Test', env=None), name='Second', state=<BindingState.
↳bound: 1>, avail=True, port=None, speed=115200)
```

2.1.5 Priorities

Each driver supports a `priorities` class variable. This allows drivers which implement the same protocol to add a priority option to each of their protocols. This way a *NetworkPowerDriver* can implement the *ResetProtocol*, but if another *ResetProtocol* driver with a higher protocol is available, it will be selected instead.

Note: Priority resolution only takes place if you have multiple drivers which implement the same protocol and you are not fetching them by name.

The target resolves the driver priority via the Method Resolution Order (MRO) of the driver's base classes. If a base class has a *priorities* dictionary which contains the requested Protocol as a key, that priority is used. Otherwise, 0 is returned as the default priority.

To set the priority of a protocol for a driver, add a class variable with the name *priorities*, e.g.

```
@attr.s
class NetworkPowerDriver(Driver, PowerProtocol, ResetProtocol):
    priorities: {PowerProtocol: -10}
```

2.1.6 Strategies

Especially when using labgrid from pytest, explicitly controlling the board's boot process can distract from the individual test case. Each *Strategy* implements the board- or project-specific actions necessary to transition from one state to another. labgrid includes the *BareboxStrategy* and the *UBootStrategy*, which can be used as-is for simple cases or serve as an example for implementing a custom strategy.

Strategies themselves are not activated/deactivated. Instead, they control the states of the other drivers explicitly and execute actions to bring the target into the requested state.

See the strategy example (`examples/strategy`) and the included strategies in `labgrid/strategy` for some more information.

For more information on the reasons behind labgrid's architecture, see *Design Decisions*.

2.2 Remote Resources and Places

labgrid contains components for accessing resources which are not directly accessible on the local machine. The main parts of this are:

labgrid-coordinator (crossbar component) Clients and exporters connect to the coordinator to publish resources, manage place configuration and handle mutual exclusion.

labgrid-exporter (CLI) Exports explicitly configured local resources to the coordinator and monitors these for changes in availability or parameters.

labgrid-client (CLI) Configures places (consisting of exported resources) and allows command line access to some actions (such as power control, bootstrap, fastboot and the console).

RemotePlace (managed resource) When used in a *Target*, the RemotePlace expands to the resources configured for the named places.

These components communicate over the [WAMP](#) implementation [Autobahn](#) and the [Crossbar](#) WAMP router.

The following sections describe the responsibilities of each component. See [Remote Access](#) for usage information.

2.2.1 Coordinator

The *Coordinator* is implemented as a Crossbar component and is started by the router. It provides separate RPC methods for the exporters and clients.

The coordinator keeps a list of all resources for clients and notifies them of changes as they occur. The resource access from clients does not pass through the coordinator, but is instead done directly from client to exporter, avoiding the need to specify new interfaces for each resource type.

The coordinator also manages the registry of “places”. These are used to configure which resources belong together from the user’s point of view. A *place* can be a generic rack location, where different boards are connected to a static set of interfaces (resources such as power, network, serial console, ...).

Alternatively, a *place* can also be created for a specific board, for example when special interfaces such as GPIO buttons need to be controlled and they are not available in the generic locations.

Each place can have aliases to simplify accessing a specific board (which might be moved between generic places). It also has a comment, which is used to store a short description of the connected board.

To support selecting a specific place from a group containing similar or identical hardware, key-value tags can be added to places and used for scheduling.

Finally, a place is configured with one or more *resource matches*. A resource match pattern has the format `<exporter>/<group>/<class>/<name>`, where each component may be replaced with the wildcard `*`. The `/<name>` part is optional and can be left out to match all resources of a class.

Some commonly used match patterns are:

/1001/ Matches all resources in groups named 1001 from all exporters.

***/1001/NetworkPowerPort** Matches only the NetworkPowerPort resource in groups named 1001 from all exporters. This is useful to exclude a NetworkSerialPort in group 1001 in cases where the serial console is connected somewhere else (such as via USB on a different exporter).

exporter1/hub1-port1/* Matches all resources exported from exporter1 in the group hub1-port1. This is an easy way to match several USB resources related to the same board (such as a USB ROM-Loader interface, Android fastboot and a USB serial gadget in Linux).

To avoid conflicting access to the same resources, a place must be *acquired* before it is used and the coordinator also keeps track of which user on which client host has currently acquired the place. The resource matches are only evaluated while a place is being acquired and cannot be changed until it is *released* again.

2.2.2 Exporter

An exporters registers all its configured resources when it connects to the router and updates the resource parameters when they change (such as (dis-)connection of USB devices). Internally, the exporter uses the normal *Resource* (and *ManagedResource*) classes as the rest of labgrid. By using *ManagedResources*, availability and parameters for resources such as USB serial ports are tracked and sent to the coordinator.

For some specific resources (such as *USBSerialPorts*), the exporter uses external tools to allow access by clients (*ser2net* in the serial port case).

Resources which do not need explicit support in the exporter, are just published as declared in the configuration file. This is useful to register externally configured resources such as network power switches or serial port servers with a labgrid coordinator.

2.2.3 Client

The client requests the current lists of resources and places from the coordinator when it connects to it and then registers for change events. Most of its functionality is exposed via the *labgrid-client* CLI tool. It is also used by the *RemotePlace* resource (see below).

Besides viewing the list of *resources*, the client is used to configure and access *places* on the coordinator. For more information on using the CLI, see the manual page for *labgrid-client*.

2.2.4 RemotePlace

To use the resources configured for a *place* to control the corresponding board (whether in pytest or directly with the labgrid library), the *RemotePlace* resource should be used. When a *RemotePlace* is configured for a *Target*, it will create a client connection to the coordinator, create additional resource objects for those configured for that place and keep them updated at runtime.

The additional resource objects can be bound to by drivers as normal and the drivers do not need to be aware that they were provided by the coordinator. For resource types which do not have an existing, network-transparent protocol (such as USB ROM loaders or JTAG interfaces), the driver needs to be aware of the mapping done by the exporter.

For generic USB resources, the exporter for example maps a *AndroidFastboot* resource to a *NetworkAndroidFastboot* resource and adds a hostname property which needs to be used by the client to connect to the exporter. To avoid the need for additional remote access protocols and authentication, labgrid currently expects that the hosts are accessible via SSH and that any file names refer to a shared filesystem (such as NFS or SMB).

Note: Using SSH's session sharing (*ControlMaster auto*, *ControlPersist*, ...) makes *RemotePlaces* easy to use even for exporters with require passwords or more complex login procedures.

For exporters which are not directly accessible via SSH, add the host to your *.ssh/config* file, with a *ProxyCommand* when need.

2.2.5 Proxy Mechanism

Both client and exporter support the proxy mechanism which uses SSH to tunnel connections to a remote host. To enable and force proxy mode on the exporter use the *-i* or *--isolated* command line option. This indicates to clients that all connections to remote resources made available by this exporter need to be tunneled using a SSH connection. On the other hand, clients may need to access the remote infrastructure using a SSH tunnel. In this case the *LG_PROXY* environment variable needs to be set to the remote host which should tunnel the connections. The client

then forwards all network traffic through SSH, even the coordinator connection is forwarded. This means that with `LG_PROXY` and `LG_CROSSBAR` labgrid can be used fully remotely with only a SSH connection as a requirement. One remaining issue here is the forward of UDP connections, which is currently not possible. UDP connections are used by some of the power backends in the form of SNMP.

Note: Labgrid prefers to connect to an isolated exporter over using the `LG_PROXY` variable. This means that for an isolated exporter, a correct entry for the exporter needs to be set up in the `~/.ssh/config` file.

3.1 Remote Access

As described in *Remote Resources and Places*, one of labgrid's main features is granting access to boards connected to other hosts transparent for the client. To get started with remote access, take a look at *Setting Up the Distributed Infrastructure*.

3.1.1 Place Scheduling

When sharing places between developers or with CI jobs, it soon becomes necessary to manage who can access which places. Developers often just need any place which has one of a group of identical devices, while CI jobs should wait until the necessary place is free instead of failing.

To support these use-cases, the coordinator has support for reserving places by using a tag filter and an optional priority. First, the places have to be tagged with the relevant key-value pairs:

```
$ labgrid-client -p board-1 set-tags board=imx6-foo
$ labgrid-client -p board-2 set-tags board=imx6-foo
$ labgrid-client -p board-3 set-tags board=imx8m-bar
$ labgrid-client -v places
Place 'board-1':
  tags: bar=baz, board=imx6-foo, jlu=2, rcz=1
  matches:
    rl-test/Testport1/NetworkSerialPort
...
Place 'board-2':
  tags: board=imx6-foo
  matches:
    rl-test/Testport2/NetworkSerialPort
...
Place 'board-3':
  tags: board=imx8m-bar
  matches:
    rl-test/Testport3/NetworkSerialPort
...
```

Now, if you want to access any `imx6-foo` board, you could find that all are already in use by someone else:

```
$ labgrid-client who
User      Host      Place      Changed
rcz       dude     board-1    2019-08-06 12:14:38.446201
jenkins   worker1  board-2    2019-08-06 12:52:44.762131
```

In this case, you can create a reservation. You can specify any custom tags as part of the filter, as well as `name=<place-name>` to select only a specific place (even if it has no custom tags).

```
$ labgrid-client reserve board=imx6-foo
Reservation 'SP37P5OQRU':
  owner: rettich/jlu
  token: SP37P5OQRU
  state: waiting
  filters:
    main: board=imx6-foo
  created: 2019-08-06 12:56:49.779982
  timeout: 2019-08-06 12:57:49.779983
```

As soon as any matching place becomes free, the reservation state will change from `waiting` to `allocated`. Then, you can use the reservation token prefixed by `+` to refer to the allocated place for locking and usage. While a place is allocated for a reservation, only the owner of the reservation can lock that place.

```
$ labgrid-client wait SP37P5OQRU
owner: rettich/jlu
token: SP37P5OQRU
state: waiting
filters:
  main: board=imx6-foo
created: 2019-08-06 12:56:49.779982
timeout: 2019-08-06 12:58:14.900621
...
owner: rettich/jlu
token: SP37P5OQRU
state: allocated
filters:
  main: board=imx6-foo
allocations:
  main: board-2
created: 2019-08-06 12:56:49.779982
timeout: 2019-08-06 12:58:46.145851
$ labgrid-client -p +SP37P5OQRU lock
acquired place board-2
$ labgrid-client reservations
Reservation 'SP37P5OQRU':
  owner: rettich/jlu
  token: SP37P5OQRU
  state: acquired
  filters:
    main: board=imx6-foo
  allocations:
    main: board-2
  created: 2019-08-06 12:56:49.779982
  timeout: 2019-08-06 12:59:11.840780
$ labgrid-client -p +SP37P5OQRU console
```

When using reservation in a CI job or to save some typing, the `labgrid-client reserve` command supports a `--shell` command to print code for evaluating in the shell. This sets the `LG_TOKEN` environment variable, which is then automatically used by `wait` and expanded via `-p +`.

```
$ eval `labgrid-client reserve --shell board=imx6-foo`
$ echo $LG_TOKEN
ZDMZJZNLBF
$ labgrid-client wait
```

(continues on next page)

(continued from previous page)

```

owner: rettich/jlu
token: ZDMZJZNLBF
state: waiting
filters:
  main: board=imx6-foo
created: 2019-08-06 13:05:30.987072
timeout: 2019-08-06 13:06:44.629736
...
owner: rettich/jlu
token: ZDMZJZNLBF
state: allocated
filters:
  main: board=imx6-foo
allocations:
  main: board-1
created: 2019-08-06 13:05:30.987072
timeout: 2019-08-06 13:06:56.196684
$ labgrid-client -p + lock
acquired place board-1
$ labgrid-client -p + show
Place 'board-1':
  tags: bar=baz, board=imx6-foo, jlu=2, rcz=1
  matches:
    rettich/Testport1/NetworkSerialPort
  acquired: rettich/jlu
  acquired resources:
    created: 2019-07-29 16:11:52.006269
    changed: 2019-08-06 13:06:09.667682
    reservation: ZDMZJZNLBF

```

Finally, to avoid calling the `wait` command explicitly, you can add `--wait` to the `reserve` command, so it waits until the reservation is allocated before returning.

A reservation will time out after a short time, if it is neither refreshed nor used by locked places.

3.2 Library

labgrid can be used directly as a Python library, without the infrastructure provided by the pytest plugin.

3.2.1 Creating and Configuring Targets

The labgrid library provides two ways to configure targets with resources and drivers: either create the *Target* directly or use *Environment* to load a configuration file.

Note: On exit of your script/application, labgrid will call `cleanup()` on the targets using the python `atexit` module.

Targets

At the lower level, a *Target* can be created directly:

```
>>> from labgrid import Target
>>> t = Target('example')
```

Next, the required *Resources* can be created:

```
>>> from labgrid.resource import RawSerialPort
>>> rsp = RawSerialPort(t, name=None, port='/dev/ttyUSB0')
```

Note: Since we support multiple drivers of the same type, resources and drivers have a required name attribute. If you don't require support for this functionality set the name to *None*.

Then, a *Driver* needs to be created on the *Target*:

```
>>> from labgrid.driver import SerialDriver
>>> sd = SerialDriver(t, name=None)
```

As the *SerialDriver* declares a binding to a *SerialPort*, the target binds it to the resource created above:

```
>>> sd.port
RawSerialPort(target=Target(name='example', env=None), name=None, state=<BindingState.
↳bound: 1>, avail=True, port='/dev/ttyUSB0', speed=115200)
>>> sd.port is rsp
True
```

Before the driver can be used, it needs to be activated:

```
>>> t.activate(sd)
>>> sd.write(b'test')
```

Active drivers can be accessed by class (any *Driver* or *Protocol*) using some syntactic sugar:

```
>>> target = Target('main')
>>> console = FakeConsoleDriver(target, 'console')
>>> target.activate(console)
>>> target[FakeConsoleDriver]
FakeConsoleDriver(target=Target(name='main', ...), name='console', ...)
>>> target[FakeConsoleDriver, 'console']
FakeConsoleDriver(target=Target(name='main', ...), name='console', ...)
```

After you are done with the target, optionally call the cleanup method on your target. While labgrid registers an atexit handler to cleanup targets, this has the advantage that exceptions can be handled by your application::

```
>>> try:
>>>     target.cleanup()
>>> except Exception as e:
>>>     <your code here>
```

Environments

In practice, it is often useful to separate the *Target* configuration from the code which needs to control the board (such as a test case or installation script). For this use-case, labgrid can construct targets from a configuration file in YAML format:


```
targets:
  example:
    resources:
      RawSerialPort:
        port: '/dev/ttyUSB0'
    drivers:
      SerialDriver: {}
```

To parse this configuration file, use the *Environment* class:

```
>>> from labgrid import Environment
>>> env = Environment('example-env.yaml')
```

Using *Environment.get_target*, the configured *Targets* can be retrieved by name. Without an argument, *get_target* would default to ‘main’:

```
>>> t = env.get_target('example')
```

To access the target’s console, the correct driver object can be found by using *Target.get_driver*:

```
>>> from labgrid.protocol import ConsoleProtocol
>>> cp = t.get_driver(ConsoleProtocol)
>>> cp
SerialDriver(target=Target(name='example', env=Environment(config_file='example.yaml
↪')), name=None, state=<BindingState.active: 2>, txdelay=0.0)
>>> cp.write(b'test')
```

When using the *get_driver* method, the driver is automatically activated. The driver activation will also wait for unavailable resources when needed.

For more information on the environment configuration files and the usage of multiple drivers, see *Environment Configuration*.

3.3 pytest Plugin

labgrid includes a *pytest* plugin to simplify writing tests which involve embedded boards. The plugin is configured by providing an environment config file (via the `-lg-env` *pytest* option, or the `LG_ENV` environment variable) and automatically creates the targets described in the environment.

Two *pytest* fixtures are provided:

env (session scope) Used to access the *Environment* object created from the configuration file. This is mostly used for defining custom fixtures at the test suite level.

target (session scope) Used to access the ‘main’ *Target* defined in the configuration file.

3.3.1 Command-Line Options

The *pytest* plugin also supports the verbosity argument of *pytest*:

- `-vv`: activates the step reporting feature, showing function parameters and/or results
- `-vvv`: activates debug logging

This allows debugging during the writing of tests and inspection during test runs.

Other labgrid-related *pytest* plugin options are:

--lg-env=LG_ENV (was **--env-config=ENV_CONFIG**) Specify a labgrid environment config file. This is equivalent to labgrid-client's `-c/--config`.

--lg-coordinator=CROSSBAR_URL Specify labgrid coordinator websocket URL. Defaults to `ws://127.0.0.1:20408/ws`. This is equivalent to labgrid-client's `-x/--crossbar`.

--lg-log=[path to logfiles] Path to store console log file. If option is specified without path the current working directory is used.

--lg-colored-steps Enables the ColoredStepReporter. Different events have different colors. The more colorful, the more important. In order to make less important output "blend into the background" different color schemes are available. See [LG_COLOR_SCHEME](#).

`pytest --help` shows these options in a separate *labgrid* section.

3.3.2 Environment Variables

LG_ENV

Behaves like LG_ENV for *labgrid-client*.

LG_COLOR_SCHEME

Influences the color scheme used for the Colored Step Reporter. `dark` (default) is meant for dark terminal background. `light` is optimized for light terminal background. Takes effect only when used with `--lg-colored-steps`.

LG_PROXY

Specifies a SSH proxy host to be used for port forwards to access the coordinator and network resources.

3.3.3 Simple Example

As a minimal example, we have a target connected via a USB serial converter (`/dev/ttyUSB0`) and booted to the Linux shell. The following environment config file (`shell-example.yaml`) describes how to access this board:

```
targets:
  main:
    resources:
      RawSerialPort:
        port: '/dev/ttyUSB0'
    drivers:
      SerialDriver: {}
      ShellDriver:
        prompt: 'root@w+: [^ ]+ '
        login_prompt: ' login: '
        username: 'root'
```

We then add the following test in a file called `test_example.py`:

```
from labgrid.protocol import CommandProtocol

def test_echo(target):
    command = target.get_driver(CommandProtocol)
```

(continues on next page)

(continued from previous page)

```
result = command.run_check('echo OK')
assert 'OK' in result
```

To run this test, we simply execute pytest in the same directory with the environment config:

```
$ pytest --lg-env shell-example.yaml --verbose
===== test session starts =====
platform linux -- Python 3.5.3, pytest-3.0.6, py-1.4.32, pluggy-0.4.0
...
collected 1 items

test_example.py::test_echo PASSED
===== 1 passed in 0.51 seconds =====
```

pytest has automatically found the test case and executed it on the target.

3.3.4 Custom Fixture Example

When writing many test cases which use the same driver, we can get rid of some common code by wrapping the *CommandProtocol* in a fixture. As pytest always executes the `conftest.py` file in the test suite directory, we can define additional fixtures there:

```
import pytest

from labgrid.protocol import CommandProtocol

@pytest.fixture(scope='session')
def command(target):
    return target.get_driver(CommandProtocol)
```

With this fixture, we can simplify the `test_example.py` file to:

```
def test_echo(command):
    result = command.run_check('echo OK')
    assert 'OK' in result
```

3.3.5 Strategy Fixture Example

When using a *Strategy* to transition the target between states, it is useful to define a function scope fixture per state in `conftest.py`:

```
import pytest

from labgrid.protocol import CommandProtocol
from labgrid.strategy import BareboxStrategy

@pytest.fixture(scope='session')
def strategy(target):
    try:
        return target.get_driver(BareboxStrategy)
    except NoDriverFoundError:
        pytest.skip("strategy not found")
```

(continues on next page)

(continued from previous page)

```
@pytest.fixture(scope='function')
def switch_off(target, strategy, capsys):
    with capsys.disabled():
        strategy.transition('off')

@pytest.fixture(scope='function')
def bootloader_command(target, strategy, capsys):
    with capsys.disabled():
        strategy.transition('barebox')
    return target.get_active_driver(CommandProtocol)

@pytest.fixture(scope='function')
def shell_command(target, strategy, capsys):
    with capsys.disabled():
        strategy.transition('shell')
    return target.get_active_driver(CommandProtocol)
```

Note: The `capsys.disabled()` context manager is only needed when using the *ManualPowerDriver*, as it will not be able to access the console otherwise. See the corresponding [pytest documentation](#) for details.

With the fixtures defined above, switching between bootloader and Linux shells is easy:

```
def test_barebox_initial(bootloader_command):
    stdout = bootloader_command.run_check('version')
    assert 'barebox' in '\n'.join(stdout)

def test_shell(shell_command):
    stdout = shell_command.run_check('cat /proc/version')
    assert 'Linux' in stdout[0]

def test_barebox_after_reboot(bootloader_command):
    bootloader_command.run_check('true')
```

Note: The *bootloader_command* and *shell_command* fixtures use *Target.get_active_driver* to get the currently active *CommandProtocol* driver (either *BareboxDriver* or *ShellDriver*). Activation and deactivation of drivers is handled by the *BareboxStrategy* in this example.

The *Strategy* needs additional drivers to control the target. Adapt the following environment config file (`strategy-example.yaml`) to your setup:

```
targets:
  main:
    resources:
      RawSerialPort:
        port: '/dev/ttyUSB0'
    drivers:
      ManualPowerDriver:
        name: 'example-board'
      SerialDriver: {}
      BareboxDriver:
        prompt: 'barebox@[:]+:[^ ]+ '
      ShellDriver:
        prompt: 'root@\w+:[^ ]+ '
```

(continues on next page)

(continued from previous page)

```
login_prompt: ' login: '
username: 'root'
BareboxStrategy: {}
```

For this example, you should get a report similar to this:

```
$ pytest --lg-env strategy-example.yaml -v
===== test session starts =====
platform linux -- Python 3.5.3, pytest-3.0.6, py-1.4.32, pluggy-0.4.0
...
collected 3 items

test_strategy.py::test_barebox_initial
main: CYCLE the target example-board and press enter
PASSED
test_strategy.py::test_shell PASSED
test_strategy.py::test_barebox_after_reboot
main: CYCLE the target example-board and press enter
PASSED

===== 3 passed in 29.77 seconds =====
```

3.3.6 Feature Flags

labgrid includes support for feature flags on a global and target scope. Adding a `@pytest.mark.lg_feature` decorator to a test ensures it is only executed if the desired feature is available:

```
import pytest

@pytest.mark.lg_feature("camera")
def test_camera(target):
    [...]
```

Here's an example environment configuration:

```
targets:
  main:
    features:
      - camera
    resources: {}
    drivers: {}
```

This would run the above test, however the following configuration would skip the test because of the missing feature:

```
targets:
  main:
    features:
      - console
    resources: {}
    drivers: {}
```

pytest will record the missing feature as the skip reason.

For tests with multiple required features, pass them as a list to pytest:

```
import pytest

@pytest.mark.lg_feature(["camera", "console"])
def test_camera(target):
    [...]
```

Features do not have to be set per target, they can also be set via the global features key:

```
features:
  - camera
targets:
  main:
    features:
      - console
    resources: {}
    drivers: {}
```

This YAML configuration would combine both the global and the target features.

3.3.7 Test Reports

pytest-html

With the `pytest-html` plugin, the test results can be converted directly to a single-page HTML report:

```
$ pip install pytest-html
$ pytest --lg-env shell-example.yaml --html=report.html
```

JUnit XML

JUnit XML reports can be generated directly by pytest and are especially useful for use in CI systems such as [Jenkins](#) with the [JUnit Plugin](#).

They can also be converted to other formats, such as HTML with [junit2html](#) tool:

```
$ pip install junit2html
$ pytest --lg-env shell-example.yaml --junit-xml=report.xml
$ junit2html report.xml
```

labgrid adds additional xml properties to a test run, these are:

- `ENV_CONFIG`: Name of the configuration file
- `TARGETS`: List of target names
- `TARGET_{NAME}_REMOTE`: optional, if the target uses a RemotePlace resource, its name is recorded here
- `PATH_{NAME}`: optional, labgrid records the name and path
- `PATH_{NAME}_GIT_COMMIT`: optional, labgrid tries to record git sha1 values for every path
- `IMAGE_{NAME}`: optional, labgrid records the name and path to the image
- `IMAGE_{NAME}_GIT_COMMIT`: optional, labgrid tries to record git sha1 values for every image

3.4 Command-Line

labgrid contains some command line tools which are used for remote access to resources. See *labgrid-client*, *labgrid-device-config* and *labgrid-exporter* for more information.

4.1 labgrid-client

4.1.1 labgrid-client interface to control boards

Author Rouven Czerwinski <r.czerwinski@pengutronix.de>

organization Labgrid-Project

Date 2017-04-15

Copyright Copyright (C) 2016-2017 Pengutronix. This library is free software; you can redistribute it and/or modify it under the terms of the GNU Lesser General Public License as published by the Free Software Foundation; either version 2.1 of the License, or (at your option) any later version.

Version 0.0.1

Manual section 1

Manual group embedded testing

SYNOPSIS

```
labgrid-client --help
labgrid-client -p <place> <command>
labgrid-client places|resources
```

DESCRIPTION

Labgrid is a scalable infrastructure and test architecture for embedded (linux) systems.

This is the client to control a boards status and interface with it on remote machines.

OPTIONS

- h, --help** display command line help
- p PLACE, --place PLACE** specify the place to operate on
- x, --crossbar-url** the crossbar url of the coordinator, defaults to `ws://127.0.0.1:20408/ws`
- c CONFIG, --config CONFIG** set the configuration file

- s STATE, --state STATE** set an initial state before executing a command, requires a configuration file and strategy
- d, --debug** enable debugging
- v, --verbose** increase verbosity
- P PROXY, --proxy PROXY** proxy connections over ssh

CONFIGURATION FILE

The configuration file follows the description in `labgrid-device-config(1)`.

ENVIRONMENT VARIABLES

Various labgrid-client commands use the following environment variable:

LG_PLACE

This variable can be used to specify a place without using the `-p` option, the `-p` option overrides it.

LG_TOKEN

This variable can be used to specify a reservation for the `wait` command and for the `+` place expansion.

LG_STATE

This variable can be used to specify a state which the device transitions into before executing a command. Requires a configuration file and a Strategy specified for the device.

LG_ENV

This variable can be used to specify the configuration file to use without using the `--config` option, the `--config` option overrides it.

LG_CROSSBAR

This variable can be used to set the default crossbar URL (instead of using the `-x` option).

LG_CROSSBAR_REALM

This variable can be used to set the default crossbar realm to use instead of `realm1`.

LG_PROXY

This variable can be used to specify a SSH proxy hostname which should be used to connect to the coordinator and any resources which are normally accessed directly.

LG_HOSTNAME

Override the hostname used when accessing a resource. Typically only useful for CI pipelines where the hostname may not be consistent between pipeline stages.

LG_USERNAME

Override the username used when accessing a resource. Typically only useful for CI pipelines where the username may not be consistent between pipeline stages.

MATCHES

Match patterns are used to assign a resource to a specific place. The format is: exporter/group/cls/name, exporter is the name of the exporting machine, group is a name defined within the exporter, cls is the class of the exported resource and name is its name. Wild cards in match patterns are explicitly allowed, * matches anything.

LABGRID-CLIENT COMMANDS

`monitor` Monitor events from the coordinator

`resources (r)` List available resources

`places (p)` List available places

`who` List acquired places by user

`show` Show a place and related resources

`create` Add a new place (name supplied by -p parameter)

`delete` Delete an existing place

`add-alias alias` Add an alias to a place

`del-alias alias` Delete an alias from a place

`set-comment comment` Update or set the place comment

`set-tags comment` Set place tags (key=value)

`add-match match` Add one (or multiple) match pattern(s) to a place, see MATCHES

`del-match match` Delete one (or multiple) match pattern(s) from a place, see MATCHES

`add-named-match match name` Add one match pattern with a name to a place

`acquire (lock)` Acquire a place

`allow user` Allow another user to access a place

`release (unlock)` Release a place

`env` Generate a labgrid environment file for a place

`power (pw) action` Change (or get) a place's power status, where action is one of get, on, off, status

`io action` Interact with GPIO (OneWire, relays, ...) devices, where action is one of high, low, get

`console (con)` Connect to the console

`fastboot arg` Run fastboot with argument

`bootstrap filename` Start a bootloader

`sd-mux action` Switch USB SD Muxer, where action is one of dut (device-under-test), host, off

`ssh` Connect via SSH

`scp` Transfer file via scp (use ‘:dir/file’ for the remote side)

`rsync` Transfer files via rsync (use ‘:dir/file’ for the remote side)

`sshfs` Mount a remote path via sshfs

`telnet` Connect via telnet

`video` Start a video stream

`tmc command` Control a USB TMC device

`write-image` Write images onto block devices (USBSDMux, USB Sticks, ...)

`reserve filter` Create a reservation

`cancel-reservation token` Cancel a pending reservation

`wait token` Wait for a reservation to be allocated

`reservations` List current reservations

ADDING NAMED RESOURCES

If a target contains multiple Resources of the same type, named matches need to be used to address the individual resources. In addition to the *match* taken by *add-match*, *add-named-match* also takes a name for the resource. The other client commands support the name as an optional parameter and will inform the user that a name is required if multiple resources are found, but no name is given.

EXAMPLES

To retrieve a list of places run:

```
$ labgrid-client places
```

To access a place, it needs to be acquired first, this can be done by running the `acquire` command and passing the placename as a `-p` parameter:

```
$ labgrid-client -p <placename> acquire
```

Open a console to the acquired place:

```
$ labgrid-client -p <placename> console
```

Add all resources with the group “example-group” to the place example-place:

```
$ labgrid-client -p example-place add-match */example-group/*/*
```

SEE ALSO

`labgrid-exporter(1)`

4.2 labgrid-device-config

4.2.1 labgrid test configuration files

Author Rouven Czerwinski <r.czerwinski@pengutronix.de>

organization Labgrid-Project

Date 2017-04-15

Copyright Copyright (C) 2016-2017 Pengutronix. This library is free software; you can redistribute it and/or modify it under the terms of the GNU Lesser General Public License as published by the Free Software Foundation; either version 2.1 of the License, or (at your option) any later version.

Version 0.0.1

Manual section 1

Manual group embedded testing

SYNOPSIS

*.yaml

DESCRIPTION

To integrate a device into a labgrid test, labgrid needs to have a description of the device and how to access it.

This manual page is divided into section, each describing one top-level yaml key.

TARGETS

The `targets:` top key configures a target, it's `drivers` and `resources`.

The top level key is the name of the target, it needs both a `resources` and `drivers` subkey. The order of instantiated `resources` and `drivers` is important, since they are parsed as an ordered dictionary and may depend on a previous driver.

For a list of available resources and drivers refer to <https://labgrid.readthedocs.io/en/latest/configuration.html>.

OPTIONS

The `options:` top key configures various options such as the `crossbar_url`.

OPTIONS KEYS

`crossbar_url` takes as parameter the URL of the crossbar (coordinator) to connect to. Defaults to `'ws://127.0.0.1:20408'`.

`crossbar_realm` takes as parameter the realm of the crossbar (coordinator) to connect to. Defaults to `'realm1'`.

IMAGES

The `images`: top key provides paths to access preconfigured images to flash onto the board. The image paths can be either relative to the YAML file or absolute.

IMAGE KEYS

The subkeys consist of image names as keys and their paths as values. The corresponding name can then be used with the appropriate tool found under TOOLS.

IMAGE EXAMPLE

Two configured images, one for the root filesystem, one for the bootloader:

```
images:
  root: "platform-v7a/images/root.img"
  boot: "platform-v7a/images/barebox.img"
```

TOOLS

The `tools`: top key provides paths to binaries such as fastboot.

TOOLS KEYS

fastboot Path to the fastboot binary

mxs-usb-loader Path to the mxs-usb-loader binary

imx-usb-loader Path to the imx-usb-loader binary

TOOLS EXAMPLE

Configure the tool path for `imx-usb-loader`:

```
tools:
  imx-usb-loader: "/opt/labgrid-helper/imx-usb-loader"
```

IMPORTS

The `imports` key is a list of files or python modules which are imported by the environment after loading the configuration. Paths relative to the configuration file are also supported. This is useful to load drivers and strategy which are contained in your testsuite, since the import is done before instantiating the targets.

IMPORTS EXAMPLE

Import a local `myfunctions.py` file:

```
imports:
- myfunctions.py
```

EXAMPLES

A sample configuration with one *main* target, accessible via SerialPort */dev/ttyUSB0*, allowing usage of the ShellDriver:

```
targets:
  main:
    resources:
      RawSerialPort:
        port: "/dev/ttyUSB0"
    drivers:
      SerialDriver: {}
      ShellDriver:
        prompt: 'root@\w+: [^ ]+ '
        login_prompt: ' login: '
        username: 'root'
```

A sample configuration with *RemotePlace*, using the tools configuration and importing the local *mystrategy.py* file. The *MyStrategy* strategy is contained in the loaded local python file:

```
targets:
  main:
    resources:
      RemotePlace:
        name: test-place
    drivers:
      SerialDriver: {}
      ShellDriver:
        prompt: 'root@\w+: [^ ]+ '
        login_prompt: ' login: '
        username: 'root'
      MyStrategy: {}
      IMXUSBLoader: {}
tools:
  imx-usb-loader: "/opt/lg-tools/imx-usb-loader"
imports:
- mystrategy.py
```

SEE ALSO

labgrid-client(1), labgrid-exporter(1)

4.3 labgrid-exporter

4.3.1 labgrid-exporter interface to control boards

Author Rouven Czerwinski <r.czerwinski@pengutronix.de>

organization Labgrid-Project

Date 2017-04-15

Copyright Copyright (C) 2016-2017 Pengutronix. This library is free software; you can redistribute it and/or modify it under the terms of the GNU Lesser General Public License as published by the Free Software Foundation; either version 2.1 of the License, or (at your option) any later version.

Version 0.0.1

Manual section 1

Manual group embedded testing

SYNOPSIS

```
labgrid-exporter --help
labgrid-exporter *.yaml
```

DESCRIPTION

Labgrid is a scalable infrastructure and test architecture for embedded (linux) systems.

This is the man page for the exporter, supporting the export of serial ports, USB devices and various other controllers.

OPTIONS

-h, --help	display command line help
-x, --crossbar-url	the crossbar url of the coordinator
-i, --isolated	enable isolated mode (always request SSH forwards)
-n, --name	the public name of the exporter
--hostname	hostname (or IP) published for accessing resources
-d, --debug	enable debug mode

-i / --isolated

This option enables isolated mode, which causes all exported resources being marked as requiring SSH connection forwarding. Isolated mode is useful when resources (such as NetworkSerialPorts) are not directly accessible from the clients. The client will then use SSH to create a port forward to the resource when needed.

-n / --name

This option is used to configure the exporter name under which resources are registered with the coordinator, which is useful when running multiple exporters on the same host. It defaults to the system hostname.

--hostname

For resources like USBSerialPort, USBGenericExport or USBSigrokExport, the exporter needs to provide a host name to set the exported value of the “host” key. If the system hostname is not resolvable via DNS, this option can be used to override this default with another name (or an IP address).

CONFIGURATION

The exporter uses a YAML configuration file which defines groups of related resources. See <<https://labgrid.readthedocs.io/en/latest/configuration.html#exporter-configuration>> for more information.

ENVIRONMENT VARIABLES

The following environment variable can be used to configure labgrid-exporter.

LG_CROSSBAR

This variable can be used to set the default crossbar URL (instead of using the `-x` option).

LG_CROSSBAR_REALM

This variable can be used to set the default crossbar realm to use instead of `realm1`.

EXAMPLES

Start the exporter with the configuration file *my-config.yaml*:

```
$ labgrid-exporter my-config.yaml
```

Same as above, but with name *myname*:

```
$ labgrid-exporter -n myname my-config.yaml
```

SEE ALSO

`labgrid-client(1)`, `labgrid-device-config(1)`

CONFIGURATION

This chapter describes the individual drivers and resources used in a device configuration. Drivers can depend on resources or other drivers, whereas resources have no dependencies.

Here the resource *RawSerialPort* provides the information for the *SerialDriver*, which in turn is needed by the *ShellDriver*. Driver dependency resolution is done by searching for the driver which implements the dependent protocol, all drivers implement one or more protocols.

5.1 Resources

5.1.1 Serial Ports

RawSerialPort

A *RawSerialPort* is a serial port which is identified via the device path on the local computer. Take note that re-plugging USB serial converters can result in a different enumeration order.

```
RawSerialPort:
  port: /dev/ttyUSB0
  speed: 115200
```

The example would access the serial port `/dev/ttyUSB0` on the local computer with a baud rate of 115200.

- port (str): path to the serial device
- speed (int): desired baud rate

Used by:

- *SerialDriver*

NetworkSerialPort

A *NetworkSerialPort* describes a serial port which is exported over the network, usually using RFC2217 or raw tcp.

```
NetworkSerialPort:
  host: remote.example.computer
  port: 53867
  speed: 115200
```

The example would access the serial port on computer `remote.example.computer` via port 53867 and use a baud rate of 115200 with the RFC2217 protocol.

- `host` (str): hostname of the remote host
- `port` (str): TCP port on the remote host to connect to
- `speed` (int): baud rate of the serial port
- `protocol` (str): optional, protocol used for connection: `raw` or `rfc2217`

Used by:

- *SerialDriver*

USBSerialPort

A `USBSerialPort` describes a serial port which is connected via USB and is identified by matching udev properties. This allows identification through hot-plugging or rebooting.

```
USBSerialPort:
  match:
    'ID_SERIAL_SHORT': 'P-00-00682'
  speed: 115200
```

The example would search for a USB serial converter with the key `ID_SERIAL_SHORT` and the value `P-00-00682` and use it with a baud rate of 115200.

- `match` (str): key and value for a udev match, see *udev Matching*
- `speed` (int): baud rate of the serial port

Used by:

- *SerialDriver*

5.1.2 Power Ports

NetworkPowerPort

A `NetworkPowerPort` describes a remotely switchable power port.

```
NetworkPowerPort:
  model: gude
  host: powerswitch.example.computer
  index: 0
```

The example describes port 0 on the remote power switch `powerswitch.example.computer`, which is a *gude* model.

- `model` (str): model of the power switch
- `host` (str): hostname of the power switch
- `index` (int): number of the port to switch

Used by:

- *NetworkPowerDriver*

PDUDaemonPort

A PDUDaemonPort describes a PDU port accessible via [PDUDaemon](#). As one PDUDaemon instance can control many PDUs, the instance name from the PDUDaemon configuration file needs to be specified.

```
PDUDaemonPort:
  host: pduserver
  pdu: apc-snmpv3-noauth
  index: 1
```

The example describes port 1 on the PDU configured as *apc-snmpv3-noauth*, with PDUDaemon running on the host *pduserver*.

- host (str): name of the host running the PDUDaemon
- pdu (str): name of the PDU in the configuration file
- index (int): index of the power port on the PDU

Used by:

- *PDUDaemonDriver*

YKUSHPowerPort

A YKUSHPowerPort describes a YEPKIT YKUSH USB (HID) switchable USB hub.

```
YKUSHPowerPort:
  serial: YK12345
  index: 1
```

The example describes port 1 on the YKUSH USB hub with the serial “YK12345”. (use “pykush -l” to get your serial...)

- serial (str): serial number of the YKUSH hub
- index (int): number of the port to switch

Used by:

- *YKUSHPowerDriver*

USBPowerPort

A USBPowerPort describes a generic switchable USB hub as supported by [uhubctl](#).

```
USBPowerPort:
  match:
    ID_PATH: pci-0000:00:14.0-usb-0:2:1.0
  index: 1
```

The example describes port 1 on the hub with the ID_PATH “pci-0000:00:14.0-usb-0:2:1.0”. (use `udevadm info /sys/bus/usb/devices/...` to find the ID_PATH value)

- index (int): number of the port to switch

Used by:

- *USBPowerDriver*

Note: Labgrid requires that the interface is contained in the ID_PATH. This usually means that the ID_PATH should end with `:1.0`. Only this first interface is registered with the `hub` driver labgrid is looking for, paths without the interface will fail to match since they use the `usb` driver.

SiSPMPowerPort

A SiSPMPowerPort describes a GEMBIRD SiS-PM as supported by `sispmctl`.

```
SiSPMPowerPort:
  match:
    ID_PATH: platform-1c1a400.usb-usb-0:2
  index: 1
```

The example describes port 1 on the hub with the ID_PATH “platform-1c1a400.usb-usb-0:2”.

- index (int): number of the port to switch

Used by:

- *SiSPMPowerDriver*

5.1.3 ModbusTCPCoil

A ModbusTCPCoil describes a coil accessible via ModbusTCP.

```
ModbusTCPCoil:
  host: "192.168.23.42"
  coil: 1
```

The example describes the coil with the address 1 on the ModbusTCP device *192.168.23.42*.

- host (str): hostname of the Modbus TCP server e.g. “192.168.23.42:502”
- coil (int): index of the coil e.g. 3
- invert (bool): optional, whether the logic level is be inverted (active-low)

Used by:

- *ModbusCoilDriver*

5.1.4 NetworkService

A NetworkService describes a remote SSH connection.

```
NetworkService:
  address: example.computer
  username: root
```

The example describes a remote SSH connection to the computer *example.computer* with the username *root*. Set the optional password `password` property to make SSH login with a password instead of the key file (needs `sshpass` to be installed)

When used with `labgrid-exporter`, the address can contain a device scope suffix (such as `%eth1`), which is especially useful with overlapping address ranges or link-local IPv6 addresses. In that case, the SSH connection will

be proxied via the exporter, using `socat` and the `labgrid-bound-connect` `sudo` helper. These and the `sudo` configuration needs to be prepared by the administrator.

- `address` (str): hostname of the remote system
- `username` (str): username used by SSH
- `password` (str): password used by SSH
- `port` (int): optional, port used by SSH (default 22)

Used by:

- *SSHDriver*

5.1.5 OneWirePIO

A `OneWirePIO` describes a onewire programmable I/O pin.

```
OneWirePIO:
  host: example.computer
  path: /29.7D6913000000/PIO.0
  invert: false
```

The example describes a `PIO.0` at device address `29.7D6913000000` via the onewire server on `example.computer`.

- `host` (str): hostname of the remote system running the onewire server
- `path` (str): path on the server to the programmable I/O pin
- `invert` (bool): optional, whether the logic level is be inverted (active-low)

Used by:

- *OneWirePIODriver*

5.1.6 USBMassStorage

A `USBMassStorage` resource describes a USB memory stick or similar device.

```
USBMassStorage:
  match:
    'ID_PATH': 'pci-0000:06:00.0-usb-0:1.3.2:1.0-scsi-0:0:0:3'
```

- `match` (str): key and value for a udev match, see *udev Matching*

Used by:

- *USBStorageDriver*

5.1.7 NetworkUSBMassStorage

A `NetworkUSBMassStorage` resource describes a USB memory stick or similar device available on a remote computer.

Used by:

- *USBStorageDriver*

The `NetworkUSBMassStorage` can be used in test cases by calling the `write_image()`, and `get_size()` functions.

5.1.8 SigrokDevice

A SigrokDevice resource describes a sigrok device. To select a specific device from all connected supported devices use the *SigrokUSBDevice*.

```
SigrokUSBDevice:  
  driver: fx2lafw  
  channel: "D0=CLK,D1=DATA"
```

- driver (str): name of the sigrok driver to use
- channel (str): optional, channel mapping as described in the sigrok-cli man page

Used by:

- *SigrokDriver*

5.1.9 IMXUSBLoader

An IMXUSBLoader resource describes a USB device in the imx loader state.

```
IMXUSBLoader:  
  match:  
    'ID_PATH': 'pci-0000:06:00.0-usb-0:1.3.2:1.0'
```

- match (str): key and value for a udev match, see *udev Matching*

Used by:

- *IMXUSBDriver*
- *UUUDriver*

5.1.10 MXSUSBLoader

An MXSUSBLoader resource describes a USB device in the mxs loader state.

```
MXSUSBLoader:  
  match:  
    'ID_PATH': 'pci-0000:06:00.0-usb-0:1.3.2:1.0'
```

- match (str): key and value for a udev match, see *udev Matching*

Used by:

- *MXSUSBDriver*
- *UUUDriver*

5.1.11 RKUSBLoader

An RKUSBLoader resource describes a USB device in the rockchip loader state.

```
RKUSBLoader:  
  match:  
    'sys_name': '1-3'
```

- match (str): key and value for a udev match, see *udev Matching*

Used by:

- *RKUSBDriver*

5.1.12 NetworkMXSUSBLoader

A NetworkMXSUSBLoader describes an *MXSUSBLoader* available on a remote computer.

5.1.13 NetworkIMXUSBLoader

A NetworkIMXUSBLoader describes an *IMXUSBLoader* available on a remote computer.

5.1.14 NetworkRKUSBLoader

A NetworkRKUSBLoader describes an *RKUSBLoader* available on a remote computer.

5.1.15 AndroidFastboot

An AndroidFastboot resource describes a USB device in the fastboot state.

```
AndroidFastboot:
  match:
    'ID_PATH': 'pci-0000:06:00.0-usb-0:1.3.2:1.0'
```

- match (str): key and value for a udev match, see *udev Matching*

Used by:

- *AndroidFastbootDriver*

5.1.16 USBEthernetInterface

A USBEthernetInterface resource describes a USB ethernet adapter.

```
USBEthernetInterface:
  match:
    'ID_PATH': 'pci-0000:06:00.0-usb-0:1.3.2:1.0'
```

- match (str): key and value for a udev match, see *udev Matching*

5.1.17 AlteraUSBBlaster

An AlteraUSBBlaster resource describes an Altera USB blaster.

```
AlteraUSBBlaster:
  match:
    'ID_PATH': 'pci-0000:06:00.0-usb-0:1.3.2:1.0'
```

- match (dict): key and value for a udev match, see *udev Matching*

Used by:

- *OpenOCDDriver*

- *QuartusHPSDriver*

5.1.18 SNMPEthernetPort

A SNMPEthernetPort resource describes a port on an Ethernet switch, which is accessible via SNMP.

```
SNMPEthernetPort:  
  switch: "switch-012"  
  interface: "17"
```

- switch (str): host name of the Ethernet switch
- interface (str): interface name

5.1.19 SigrokUSBDevice

A SigrokUSBDevice resource describes a sigrok USB device.

```
SigrokUSBDevice:  
  driver: fx2lafw  
  channel: "D0=CLK,D1=DATA"  
  match:  
    'ID_PATH': 'pci-0000:06:00.0-usb-0:1.3.2:1.0'
```

- driver (str): name of the sigrok driver to use
- channel (str): optional, channel mapping as described in the sigrok-cli man page
- match (str): key and value for a udev match, see *udev Matching*

Used by:

- *SigrokDriver*

5.1.20 NetworkSigrokUSBDevice

A NetworkSigrokUSBDevice resource describes a sigrok USB device connected to a host which is exported over the network. The SigrokDriver will access it via SSH.

```
NetworkSigrokUSBDevice:  
  driver: fx2lafw  
  channel: "D0=CLK,D1=DATA"  
  match:  
    'ID_PATH': 'pci-0000:06:00.0-usb-0:1.3.2:1.0'  
  host: remote.example.computer
```

- driver (str): name of the sigrok driver to use
- channel (str): optional, channel mapping as described in the sigrok-cli man page
- match (str): key and value for a udev match, see *udev Matching*

Used by:

- *SigrokDriver*

5.1.21 SigrokUSBSerialDevice

A `SigrokUSBSerialDevice` resource describes a sigrok device which communicates of a USB serial port instead of being a USB device itself (see *SigrokUSBDevice* for that case).

```
SigrokUSBSerialDevice:
  driver: manson-hcs-3xxx
  match:
    '@ID_SERIAL_SHORT': P-00-02389
```

- driver (str): name of the sigrok driver to use

Used by:

- *SigrokPowerDriver*

5.1.22 USBSDMuxDevice

A *USBSDMuxDevice* resource describes a Pengutronix **USB-SD-Mux** device.

```
USBSDMuxDevice:
  match:
    '@ID_PATH': 'pci-0000:00:14.0-usb-0:1.2'
```

- match (str): key and value for a udev match, see *udev Matching*

Used by:

- *USBSDMUXDriver*

5.1.23 NetworkUSBSDMuxDevice

A *NetworkUSBSDMuxDevice* resource describes a *USBSDMuxDevice* available on a remote computer.

5.1.24 USBSDWireDevice

A *USBSDWireDevice* resource describes a Tizen **SD Wire** device device.

```
USBSDWireDevice:
  match:
    '@ID_PATH': 'pci-0000:00:14.0-usb-0:1.2'
```

- match (str): key and value for a udev match, see *udev Matching*

Used by:

- *USBSDWireDriver*

5.1.25 NetworkUSBSDWireDevice

A *NetworkUSBSDWireDevice* resource describes a *USBSDWireDevice* available on a remote computer.

5.1.26 USBVideo

A *USBVideo* resource describes a USB video camera which is supported by a Video4Linux2 kernel driver.

```
USBVideo:
  match:
    '@ID_PATH': 'pci-0000:00:14.0-usb-0:1.2'
```

Used by:

- *USBVideoDriver*

5.1.27 NetworkUSBVideo

A *NetworkUSBVideo* resource describes a *USBVideo* resource available on a remote computer.

5.1.28 USBTMC

A *USBTMC* resource describes an oscilloscope connected via the USB TMC protocol. The low-level communication is handled by the `usbtmc` kernel driver.

```
USBTMC:
  match:
    '@ID_PATH': 'pci-0000:00:14.0-usb-0:1.2'
```

A udev rules file may be needed to allow access for non-root users:

```
DRIVERS=="usbtmc", MODE="0660", GROUP="plugdev"
```

Used by:

- *USBTMCDriver*

5.1.29 NetworkUSBTMC

A *NetworkUSBTMC* resource describes a *USBTMC* resource available on a remote computer.

5.1.30 Flashrom

A *Flashrom* resource is used to configure the parameters to a local installed flashrom instance. It is assumed that flashrom is installed on the host and the executable is configured in:

```
tools:
  flashrom: '/usr/sbin/flashrom'
```

The resource must configure which programmer to use and the parameters to the programmer. The programmer parameter is passed directly to the flashrom bin hence `man(8) flashrom` can be used for reference. Below an example where the local spidev is used.

```
Flashrom:
  programmer: 'linux_spi:dev=/dev/spidev0.1,spispeed=30000'
```

Used by:

- *FlashromDriver*

5.1.31 NetworkFlashRom

A NetworkFlashrom describes an *Flashrom* available on a remote computer.

5.1.32 XenaManager

A XenaManager resource describes a Xena Manager instance which is the instance the *XenaDriver* must connect to in order to configure a Xena chassis.

```
XenaManager:
  hostname: "example.computer"
```

Used by:

- *XenaDriver*

5.1.33 PyVISADevice

A PyVISADevice resource describes a test stimuli device controlled by PyVISA. Such device could be a signal generator.

```
PyVISADevice:
  type: "TCPIP"
  url: "192.168.110.11"
```

- type (str): device resource type following the pyVISA resource syntax, e.g. ASRL, TCPIP...
- url (str): device identifier on selected resource, e.g. <ip> for TCPIP resource

Used by:

- *PyVISADriver*

5.1.34 RemotePlace

A RemotePlace describes a set of resources attached to a labgrid remote place.

```
RemotePlace:
  name: example-place
```

The example describes the remote place *example-place*. It will connect to the labgrid remote coordinator, wait until the resources become available and expose them to the internal environment.

- name (str): name or pattern of the remote place

Used by:

- potentially all drivers

5.1.35 DockerDaemon

A `DockerDaemon` describes where to contact a docker daemon process. `DockerDaemon` also participates in managing `NetworkService` instances created through interaction with that daemon.

```
DockerDaemon:
  docker_daemon_url: 'unix:///var/run/docker.sock'
```

The example describes a docker daemon accessible via the `'/var/run/docker.sock'` unix socket. When used by a `DockerDriver`, the `DockerDriver` will first create a docker container which the `DockerDaemon` resource will subsequently use to create one/more `NetworkService` instances - as specified by `DockerDriver` configuration. Each `NetworkService` instance corresponds to a network service running inside the container.

Moreover, `DockerDaemon` will remove any hanging containers if `DockerDaemon` is used several times in a row - as is the case when executing test suites. Normally `DockerDriver` - when deactivated - cleans up the created docker container; programming errors, keyboard interrupts or unix kill signals may lead to hanging containers, however; therefore auto-cleanup is important.

- `docker_daemon_url` (str): The url of the daemon to use for this target.

Used by:

- `DockerDriver`

5.1.36 LXAIOPBusPIO

An `LXAIOPBusPIO` resource describes a single PIO pin on an `LXAIOPBusNode`.

```
LXAIOPBusPIO:
  host: localhost:8080
  node: IOMux-00000003
  pin: OUT0
  invert: False
```

The example uses an `lxa-io-bus-server` running on `localhost:8080`, with node `IOMux-00000003` and pin `OUT0`.

- `host` (str): hostname with port of the `lxa-io-bus` server
- `node` (str): name of the node to use
- `pin` (str): name of the pin to use
- `invert` (bool): whether to invert the pin

Used by:

- `LXAIOPBusPIODriver`

5.1.37 NetworkLXAIOPBusPIO

A `NetworkLXAIOPBusPIO` describes an `LXAIOPBusPIO` exported over the network.

5.1.38 udev Matching

udev matching allows labgrid to identify resources via their udev properties. Any udev property key and value can be used, path matching USB devices is allowed as well. This allows exporting a specific USB hub port or the correct identification of a USB serial converter across computers.

The initial matching and monitoring for udev events is handled by the *UdevManager* class. This manager is automatically created when a resource derived from *USBResource* (such as *USBSerialPort*, *IMXUSBLoader* or *AndroidFastboot*) is instantiated.

To identify the kernel device which corresponds to a configured *USBResource*, each existing (and subsequently added) kernel device is matched against the configured resources. This is based on a list of *match entries* which must all be tested successfully against the potential kernel device. Match entries starting with an @ are checked against the device's parents instead of itself; here one matching parent causes the check to be successful.

A given *USBResource* class has builtin match entries that are checked first, for example that the `SUBSYSTEM` is `tty` as in the case of the *USBSerialPort*. Only if these succeed, match entries provided by the user for the resource instance are considered.

In addition to the properties reported by `udevadm monitor --udev --property`, elements of the `ATTR(S){}` dictionary (as shown by `udevadm info <device> -a`) are useable as match keys. Finally `sys_name` allows matching against the name of the directory in `sysfs`. All match entries must succeed for the device to be accepted.

The following examples show how to use the udev matches for some common use-cases.

Matching a USB Serial Converter on a Hub Port

This will match any USB serial converter connected below the hub port 1.2.5.5 on bus 1. The `sys_name` value corresponds to the hierarchy of buses and ports as shown with `lsusb -t` and is also usually displayed in the kernel log messages when new devices are detected.

```
USBSerialPort:
match:
    '@sys_name': '1-1.2.5.5'
```

Note the @ in the `@sys_name` match, which applies this match to the device's parents instead of directly to itself. This is necessary for the *USBSerialPort* because we actually want to find the `ttyUSB?` device below the USB serial converter device.

Matching an Android Fastboot Device

In this case, we want to match the USB device on that port directly, so we don't use a parent match.

```
AndroidFastboot:
match:
    'sys_name': '1-1.2.3'
```

Matching a Specific UART in a Dual-Port Adapter

On this board, the serial console is connected to the second port of an on-board dual-port USB-UART. The board itself is connected to the bus 3 and port path 10.2.2.2. The correct value can be shown by running `udevadm info /dev/ttyUSB9` in our case:

```
$ udevadm info /dev/ttyUSB9
P: /devices/pci0000:00/0000:00:14.0/usb3/3-10/3-10.2/3-10.2.2/3-10.2.2.2/3-10.2.2.2:1.
↳ 1/ttyUSB9/tty/ttyUSB9
N: ttyUSB9
S: serial/by-id/usb-FTDI_Dual_RS232-HS-if01-port0
S: serial/by-path/pci-0000:00:14.0-usb-0:10.2.2.2:1.1-port0
```

(continues on next page)

(continued from previous page)

```

E: DEVLINKS=/dev/serial/by-id/usb-FTDI_Dual_RS232-HS-if01-port0 /dev/serial/by-path/
→pci-0000:00:14.0-usb-0:10.2.2.2:1.1-port0
E: DEVNAME=/dev/ttyUSB9
E: DEVPATH=/devices/pci0000:00/0000:00:14.0/usb3/3-10/3-10.2/3-10.2.2/3-10.2.2.2/3-10.
→2.2.2:1.1/ttyUSB9/tty/ttyUSB9
E: ID_BUS=usb
E: ID_MODEL=Dual_RS232-HS
E: ID_MODEL_ENC=Dual\x20RS232-HS
E: ID_MODEL_FROM_DATABASE=FT232C Dual USB-UART/FIFO IC
E: ID_MODEL_ID=6010
E: ID_PATH=pci-0000:00:14.0-usb-0:10.2.2.2:1.1
E: ID_PATH_TAG=pci-0000_00_14_0-usb-0_10_2_2_1_1
E: ID_REVISION=0700
E: ID_SERIAL=FTDI_Dual_RS232-HS
E: ID_TYPE=generic
E: ID_USB_DRIVER=ftdi_sio
E: ID_USB_INTERFACES=:fffff:
E: ID_USB_INTERFACE_NUM=01
E: ID_VENDOR=FTDI
E: ID_VENDOR_ENC=FTDI
E: ID_VENDOR_FROM_DATABASE=Future Technology Devices International, Ltd
E: ID_VENDOR_ID=0403
E: MAJOR=188
E: MINOR=9
E: SUBSYSTEM=tty
E: TAGS=:systemd:
E: USEC_INITIALIZED=9129609697

```

We use the `ID_USB_INTERFACE_NUM` to distinguish between the two ports:

```

USBSerialPort:
match:
    '@sys_name': '3-10.2.2.2'
    'ID_USB_INTERFACE_NUM': '01'

```

Matching a USB UART by Serial Number

Most of the USB serial converters in our lab have been programmed with unique serial numbers. This makes it easy to always match the same one even if the USB topology changes or a board has been moved between host systems.

```

USBSerialPort:
match:
    'ID_SERIAL_SHORT': 'P-00-00679'

```

To check if your device has a serial number, you can use `udevadm info`:

```

$ udevadm info /dev/ttyUSB5 | grep SERIAL_SHORT
E: ID_SERIAL_SHORT=P-00-00679

```


5.2 Drivers

5.2.1 SerialDriver

A SerialDriver connects to a serial port. It requires one of the serial port resources.

Binds to:

port:

- *NetworkSerialPort*
- *RawSerialPort*
- *USBSerialPort*

```
SerialDriver:
txdelay: 0.05
```

Implements:

- *ConsoleProtocol*

Arguments:

- txdelay (float): time in seconds to wait before sending each byte
- timeout (float): time in seconds to wait for a network serial port before an error occurs. Default is 3 seconds.

5.2.2 ShellDriver

A ShellDriver binds on top of a *ConsoleProtocol* and is designed to interact with a login prompt and a Linux shell.

Binds to:

console:

- *ConsoleProtocol*

Implements:

- *CommandProtocol*

```
ShellDriver:
prompt: 'root@\w+: [^ ]+ '
login_prompt: ' login: '
username: 'root'
```

Arguments:

- prompt (regex): shell prompt to match after logging in
- login_prompt (regex): match for the login prompt
- username (str): username to use during login
- password (str): password to use during login
- keyfile (str): optional keyfile to upload after login, making the *SSHDriver* usable
- login_timeout (int): optional, timeout for login prompt detection in seconds (default 60)

- `await_login_timeout` (int): optional, time in seconds of silence that needs to pass before sending a newline to device.
- `console_ready` (regex): optional, pattern used by the kernel to inform the user that a console can be activated by pressing enter.

5.2.3 SSHDriver

A `SSHDriver` requires a `NetworkService` resource and allows the execution of commands and file upload via network. It uses SSH's `ServerAliveInterval` option to detect failed connections.

If a shared SSH connection to the target is already open, it will reuse it when running commands. In that case, `ServerAliveInterval` should be set outside of labgrid, as it cannot be enabled for an existing connection.

Binds to:

networkservice:

- `NetworkService`

Implements:

- `CommandProtocol`
- `FileTransferProtocol`

```
SSHDriver:
    keyfile: example.key
```

Arguments:

- `keyfile` (str): filename of private key to login into the remote system (only used if password is not set)
- **`stderr_merge` (bool): set to True to make `run()` return stderr merged with stdout**, and an empty list as second element.

5.2.4 UBootDriver

A `UBootDriver` interfaces with a U-Boot bootloader via a `ConsoleProtocol`.

Binds to:

console:

- `ConsoleProtocol`

Implements:

- `CommandProtocol`

```
UBootDriver:
    prompt: 'Uboot> '
```

Arguments:

- `prompt` (regex): U-Boot prompt to match
- `autoboot` (regex, default="stop autoboot"): autoboot message to match
- `password` (str): optional, U-Boot unlock password
- `interrupt` (str, default="\n"): string to interrupt autoboot (use "\x03" for CTRL-C)

- `init_commands` (tuple): tuple of commands to execute after matching the prompt
- `password_prompt` (str): optional, regex to match the U-Boot password prompt, defaults to “enter Password:”
- `boot_expression` (str): optional, regex to match the U-Boot start string defaults to “U-Boot 20d+”
- `bootstring` (str): optional, regex to match on Linux Kernel boot
- `boot_command` (str): optional, boot command for booting target (default ‘run bootcmd’)
- `login_timeout` (int): optional, timeout for login prompt detection in seconds (default 60)

5.2.5 SmallUBootDriver

A SmallUBootDriver interfaces with stripped-down U-Boot variants that are sometimes used in cheap consumer electronics.

SmallUBootDriver is meant as a driver for U-Boot with only little functionality compared to a standard U-Boot. Especially it copes with the following limitations:

- The U-Boot does not have a real password-prompt but can be activated by entering a “secret” after a message was displayed.
- The command line does not have a built-in echo command. Thus this driver uses ‘Unknown Command’ messages as marker before and after the output of a command.
- Since there is no echo we cannot return the exit code of the command. Commands will always return 0 unless the command was not found.

This driver needs the following features activated in U-Boot to work:

- The U-Boot must not have a real password prompt. Instead it must be keyword activated. For example it should be activated by a dialog like the following:
 - U-Boot: “Autobooting in 1s...”
 - labgrid: “secret”
 - U-Boot: <switching to console>
- The U-Boot must be able to parse multiple commands in a single line separated by “;”.
- The U-Boot must support the “bootm” command to boot from a memory location.

Binds to:

- *ConsoleProtocol* (see *SerialDriver*)

Implements:

- *CommandProtocol*

```
SmallUBootDriver:
    prompt: 'apl43-2\.0> '
    boot_expression: 'Autobooting in 1 seconds'
    boot_secret: "tpl"
```

Arguments:

- `prompt` (regex): U-Boot prompt to match
- `init_commands` (tuple): tuple of commands to execute after matching the prompt
- `boot_secret` (str): optional, secret used to unlock prompt

- `boot_expression` (str): optional, regex to match the U-Boot start string defaults to “U-Boot 20d+”
- `login_timeout` (int): optional, timeout for the password/login detection

5.2.6 BareboxDriver

A BareboxDriver interfaces with a barebox bootloader via a *ConsoleProtocol*.

Binds to:

console:

- *ConsoleProtocol*

Implements:

- *CommandProtocol*

```
BareboxDriver:  
prompt: 'barebox@[^:]+:[^ ]+ '
```

Arguments:

- `prompt` (regex): barebox prompt to match
- `autoboot` (regex, default=”stop autoboot”): autoboot message to match
- `interrupt` (str, default=”\n”): string to interrupt autoboot (use “\x03” for CTRL-C)
- `bootstring` (regex, default=”Linux version d”): succesfully jumped into the kernel
- `password` (str): optional, password to use for access to the shell
- `login_timeout` (int): optional, timeout for access to the shell

5.2.7 ExternalConsoleDriver

An ExternalConsoleDriver implements the *ConsoleProtocol* on top of a command executed on the local computer.

Implements:

- *ConsoleProtocol*

```
ExternalConsoleDriver:  
cmd: 'microcom /dev/ttyUSB2'  
txdelay: 0.05
```

Arguments:

- `cmd` (str): command to execute and then bind to.
- `txdelay` (float): time in seconds to wait before sending each byte

5.2.8 AndroidFastbootDriver

An AndroidFastbootDriver allows the upload of images to a device in the USB fastboot state.

Binds to:

fastboot:

- *AndroidFastboot*

Implements:

- None (yet)

AndroidFastbootDriver:

```
image: mylocal.image
sparse_size: 100M
```

Arguments:

- image (str): filename of the image to upload to the device
- sparse_size (str): optional, sparse files greater than given size (see fastboot manpage -S option for allowed size suffixes). The default is the same as the fastboot default, which is computed after querying the target's max-download-size variable.

5.2.9 OpenOCDDriver

An OpenOCDDriver controls OpenOCD to bootstrap a target with a bootloader.

Note that OpenOCD supports specifying USB paths since [a1b308ab](#) which is not part of a release yet. The OpenOCD-Driver passes the resource's USB path. Depending on which OpenOCD version is installed it is either used correctly or a warning is displayed and the first resource seen is used, which might be the wrong USB device. Consider updating your OpenOCD version when using multiple USB Blasters.

Binds to:**interface:**

- *AlteraUSBBlaster*

Implements:

- *BootstrapProtocol*

Arguments:

- config (str): OpenOCD configuration file
- search (str): include search path for scripts
- image (str): filename of image to bootstrap onto the device

5.2.10 QuartusHPSDriver

A QuartusHPSDriver controls the “Quartus Prime Programmer and Tools” to flash a target's QSPI.

Binds to:

- *AlteraUSBBlaster*

Implements:

- None

Arguments:

- image (str): filename of image to flash QSPI

The driver can be used in test cases by calling the *flash* function. An example strategy is included in labgrid.

5.2.11 ManualPowerDriver

A ManualPowerDriver requires the user to control the target power states. This is required if a strategy is used with the target, but no automatic power control is available.

Implements:

- *PowerProtocol*

```
ManualPowerDriver:
  name: 'example-board'
```

Arguments:

- name (str): name of the driver (will be displayed during interaction)

5.2.12 ExternalPowerDriver

An ExternalPowerDriver is used to control a target power state via an external command.

Implements:

- *PowerProtocol*

```
ExternalPowerDriver:
  cmd_on: example_command on
  cmd_off: example_command off
  cmd_cycle: example_command cycle
```

Arguments:

- cmd_on (str): command to turn power to the board on
- cmd_off (str): command to turn power to the board off
- cycle (str): optional command to switch the board off and on
- delay (float): configurable delay in seconds between off and on if cycle is not set

5.2.13 NetworkPowerDriver

A NetworkPowerDriver controls a *NetworkPowerPort*, allowing control of the target power state without user interaction.

Binds to:

port:

- *NetworkPowerPort*

Implements:

- *PowerProtocol*

```
NetworkPowerDriver:
  delay: 5.0
```

Arguments:

- delay (float): optional delay in seconds between off and on

5.2.14 PDUDaemonDriver

A PDUDaemonDriver controls a *PDUDaemonPort*, allowing control of the target power state without user interaction.

Note: PDUDaemon processes commands in the background, so the actual state change may happen several seconds after calls to PDUDaemonDriver return.

Binds to:

port:

- *PDUDaemonPort*

Implements:

- *PowerProtocol*

```
PDUDaemonDriver:
    delay: 5
```

Arguments:

- delay (int): optional delay in seconds between off and on

5.2.15 YKUSHPowerDriver

A YKUSHPowerDriver controls a *YKUSHPowerPort*, allowing control of the target power state without user interaction.

Binds to:

port:

- *YKUSHPowerPort*

Implements:

- *PowerProtocol*

```
YKUSHPowerDriver:
    delay: 5.0
```

Arguments:

- delay (float): optional delay in seconds between off and on

5.2.16 DigitalOutputPowerDriver

A DigitalOutputPowerDriver can be used to control the power of a Device using a DigitalOutputDriver.

Using this driver you probably want an external relay to switch the power of your DUT.

Binds to:

output:

- *DigitalOutputProtocol*

```
DigitalOutputPowerDriver:
    delay: Delay for a power cycle
```

Arguments:

- delay (float): configurable delay in seconds between off and on

5.2.17 USBPowerDriver

A USBPowerDriver controls a *USBPowerPort*, allowing control of the target power state without user interaction.

Binds to:

- *USBPowerPort*

Implements:

- *PowerProtocol*

```
USBPowerPort:
    delay: 5.0
```

Arguments:

- delay (float): optional delay in seconds between off and on

5.2.18 SiSPMPowerDriver

A SiSPMPowerDriver controls a *SiSPMPowerPort*, allowing control of the target power state without user interaction.

Binds to:

- *SiSPMPowerPort*

Implements:

- *PowerProtocol*

```
SiSPMPowerPort:
    delay: 5.0
```

Arguments:

- delay (float): optional delay in seconds between off and on

5.2.19 GpioDigitalOutputDriver

The GpioDigitalOutputDriver writes a digital signal to a GPIO line.

This driver configures GPIO lines via *the sysfs kernel interface* <<https://www.kernel.org/doc/html/latest/gpio/sysfs.html>>. While the driver automatically exports the GPIO, it does not configure it in any other way than as an output.

Implements:

- *DigitalOutputProtocol*

```
GpioDigitalOutputDriver:
    index: 42
```


Arguments:

- `index` (int): The index of a GPIO line

5.2.20 SerialPortDigitalOutputDriver

The `SerialPortDigitalOutputDriver` makes it possible to use a UART as a 1-Bit general-purpose digital output.

This driver acts on top of a `SerialDriver` and uses the its pyserial port to control the flow control lines.

Implements:

- *`DigitalOutputProtocol`*

```
SerialPortDigitalOutputDriver:
  signal: "DTR"
  bindings: { serial : "nameOfSerial" }
```

Arguments:

- `signal` (str): control signal to use: DTR or RTS
- `bindings` (dict): A named ressource of the type `SerialDriver` to bind against. This is only needed if you have multiple `SerialDriver` in your environment (what is likely to be the case if you are using this driver).
- `invert` (bool): whether to invert the signal

5.2.21 FileDigitalOutputDriver

The `FileDigitalOutputDriver` uses a file to write arbitrary string representations of booleans to a file and read from it.

The file is checked to exist at configuration time.

If the file's content does not match any of the representations reading defaults to False.

A prime example for using this driver is Linux's sysfs.

Implements:

- *`DigitalOutputProtocol`*

```
FileDigitalOutputDriver:
  filepath: "/sys/class/leds/myled/brightness"
```

Arguments:

- `filepath` (str): A file that is used for reads and writes.
- `false_repr` (str): A representation for False (default: "0n")
- `true_repr` (str): A representation for True (default: "1n")

5.2.22 ModbusCoilDriver

A `ModbusCoilDriver` controls a *`ModbusTCPCoil`* resource. It can set and get the current state of the resource.

Binds to:**coil:**

- *`ModbusTCPCoil`*

Implements:

- *DigitalOutputProtocol*

```
ModbusCoilDriver: {}
```

Arguments:

- None

5.2.23 MXSUSBDriver

A MXSUSBDriver is used to upload an image into a device in the mxs USB loader state. This is useful to bootstrap a bootloader onto a device.

Binds to:**loader:**

- *MXSUSBLoader*
- *NetworkMXSUSBLoader*

Implements:

- *BootstrapProtocol*

```
targets:
  main:
    drivers:
      MXSUSBDriver:
        image: mybootloaderkey

images:
  mybootloaderkey: path/to/mybootloader.img
```

Arguments:

- image (str): The key in *images* containing the path of an image to bootstrap onto the target

5.2.24 IMXUSBDriver

A IMXUSBDriver is used to upload an image into a device in the imx USB loader state. This is useful to bootstrap a bootloader onto a device.

Binds to:**loader:**

- *IMXUSBLoader*
- *NetworkIMXUSBLoader*

Implements:

- *BootstrapProtocol*

```
targets:
  main:
    drivers:
      IMXUSBDriver:
```

(continues on next page)

(continued from previous page)

```

    image: mybootloaderkey

images:
    mybootloaderkey: path/to/mybootloader.img

```

Arguments:

- image (str): The key in *images* containing the path of an image to bootstrap onto the target

5.2.25 RKUSBDriver

A RKUSBDriver is used to upload an image into a device in the rockchip USB loader state. This is useful to bootstrap a bootloader onto a device.

Binds to:**loader:**

- *RKUSBLoader*
- *NetworkRKUSBLoader*

Implements:

- *BootstrapProtocol*

```

targets:
    main:
        drivers:
            RKUSBDriver:
                image: mybootloaderkey
                usb_loader: myloaderkey

images:
    mybootloaderkey: path/to/mybootloader.img
    myloaderkey: path/to/myloader.bin

```

Arguments:

- image (str): The key in *images* containing the path of an image to bootstrap onto the target
- usb_loader (str): The key in *images* containing the path of an image to bootstrap onto the target

5.2.26 UUUDriver

A UUUDriver is used to upload an image into a device in the NXP USB loader state. This is useful to bootstrap a bootloader onto a device.

Binds to:**loader:**

- *MXSUSBLoader*
- *NetworkMXSUSBLoader*
- *IMXUSBLoader*
- *NetworkIMXUSBLoader*

Implements:

- *BootstrapProtocol*

```
targets:
  main:
    drivers:
      UUUDriver:
        image: mybootloaderkey
        cmd: spl
images:
  mybootloaderkey: path/to/mybootloader.img
```

Arguments:

- image (str): The key in *images* containing the path of an image to bootstrap onto the target
- cmd (str): single command used for mfgtool (default: spl)

5.2.27 USBStorageDriver

A USBStorageDriver allows access to a USB stick or similar local or remote device.

Binds to:

- *USBMassStorage*
- *NetworkUSBMassStorage*

Implements:

- None (yet)

```
USBStorageDriver:
  image: flashimage
```

```
images:
  flashimage: ../images/myusb.image
```

Arguments:

- image (str): filename of the image to write to the remote usb storage

5.2.28 OneWirePIODriver

A OneWirePIODriver controls a *OneWirePIO* resource. It can set and get the current state of the resource.

Binds to:**port:**

- *OneWirePIO*

Implements:

- *DigitalOutputProtocol*

```
OneWirePIODriver: {}
```

Arguments:

- None

5.2.29 QEMUDriver

The QEMUDriver allows the usage of a QEMU instance as a target. It requires several arguments, listed below. The kernel, flash, rootfs and dtb arguments refer to images and paths declared in the environment configuration.

Binds to:

- None

```
QEMUDriver:
  qemu_bin: qemu_arm
  machine: vexpress-a9
  cpu: cortex-a9
  memory: 512M
  boot_args: "root=/dev/root console=ttyAMA0,115200"
  extra_args: ""
  kernel: kernel
  rootfs: rootfs
  dtb: dtb
```

```
tools:
  qemu_arm: /bin/qemu-system-arm
paths:
  rootfs: ../images/root
images:
  dtb: ../images/mydtb.dtb
  kernel: ../images/vmlinuz
```

Implements:

- *ConsoleProtocol*
- *PowerProtocol*

Arguments:

- qemu_bin (str): reference to the tools key for the QEMU binary
- machine (str): QEMU machine type
- cpu (str): QEMU cpu type
- memory (str): QEMU memory size (ends with M or G)
- extra_args (str): extra QEMU arguments, they are passed directly to the QEMU binary
- boot_args (str): optional, additional kernel boot argument
- kernel (str): optional, reference to the images key for the kernel
- disk (str): optional, reference to the images key for the disk image
- flash (str): optional, reference to the images key for the flash image
- rootfs (str): optional, reference to the paths key for use as the virtio-9p filesystem
- dtb (str): optional, reference to the image key for the device tree

The QEMUDriver also requires the specification of:

- a tool key, this contains the path to the QEMU binary

- an image key, the path to the kernel image and optionally the dtb key to specify the build device tree
- a path key, this is the path to the rootfs

5.2.30 SigrokDriver

The SigrokDriver uses a SigrokDevice resource to record samples and provides them during test runs.

Binds to:

sigrok:

- *SigrokUSBDevice*
- *SigrokDevice*
- *NetworkSigrokUSBDevice*

Implements:

- None yet

The driver can be used in test cases by calling the *capture*, *stop* and *analyze* functions.

5.2.31 SigrokPowerDriver

The SigrokPowerDriver uses a *SigrokUSBSerialDevice* resource to control a programmable power supply.

Binds to:

sigrok:

- *SigrokUSBSerialDevice*
- *NetworkSigrokUSBSerialDevice*

Implements:

- *PowerProtocol*

```
SigrokPowerDriver:  
delay: 3.0
```

Arguments:

- delay (float): optional delay in seconds between off and on, defaults to 3.0
- max_voltage (float): maximum allowed voltage for protection against accidental damage (optional, in volts)
- max_current (float): maximum allowed current for protection against accidental damage (optional, in ampere)

5.2.32 USBSDMuxDriver

The *USBSDMuxDriver* uses a USBSDMuxDevice resource to control a USB-SD-Mux device via *usbndmux* tool.

Implements:

- None yet

The driver can be used in test cases by calling the *set_mode()* function with argument being *dut*, *host*, *off*, or *client*.

5.2.33 USBSDWireDriver

The *USBSDWireDriver* uses a USBSDWireDevice resource to control a USB-SD-Wire device via `sd-mux-ctrl` tool.

Implements:

- None yet

The driver can be used in test cases by calling the `set_mode()` function with argument being *dut*, *host*, *off*, or *client*.

5.2.34 USBVideoDriver

The *USBVideoDriver* is used to show a video stream from a remote USB video camera in a local window. It uses the GStreamer command line utility `gst-launch` on both sides to stream the video via an SSH connection to the exporter.

Binds to:

video:

- *USBVideo*
- *NetworkUSBVideo*

Implements:

- None yet

Although the driver can be used from Python code by calling the `stream()` method, it is currently mainly useful for the `video` subcommand of `labgrid-client`. It supports the *Logitech HD Pro Webcam C920* with the USB ID 046d:082d, but other cameras can be added to `get_caps()` in `labgrid/driver/usbvideodriver.py`.

5.2.35 USBTMCDriver

The *USBTMCDriver* is used to control a oscilloscope via the USB TMC protocol.

Binds to:

tmc:

- *USBTMC*
- *NetworkUSBTMC*

Implements:

- None yet

Currently, it can be used by the `labgrid-client` `tmc` subcommands to show (and save) a screenshot, to show per channel measurements and to execute raw TMC commands. It only supports the *Keysight DSO-X 2000* series (with the USB ID 0957:1798), but more devices can be added by extending `on_activate()` in `labgrid/driver/usbtmcdriver.py` and writing a corresponding backend in `labgrid/driver/usbtmc/`.

5.2.36 FlashromDriver

The *FlashromDriver* is used to flash a rom, using the flashrom utility.

```
FlashromDriver:
    image: 'foo'
images:
    foo: ../images/image_to_load.raw
```

Binds to:**flashrom_resource:**

- *Flashrom*
- *NetworkFlashrom*

The FlashromDriver allows using the linux util “flashrom” to write directly to a ROM e.g. a NOR SPI flash. The assumption is that the device flashing the DUT e.g. an exporter is wired to the Flash to be flashed. The driver implements the bootstrap protocol. The driver uses tool configuration section and the key: flashrom to determine the path of the installed flashrom utility.

5.2.37 XenaDriver

The XenaDriver allows to use Xena networking test equipment. Using the *xenavalkyrie* library a full API to control the tester is available.

Binds to:**xena_manager:**

- *XenaManager*

The driver is supposed to work with all Xena products from the “Valkyrie Layer 2-3 Test platform” Currently tested on a *XenaCompact* chassis equipped with a *1 GE test module*.

5.2.38 DockerDriver

A DockerDriver binds to a *DockerDaemon* and is used to create and control one docker container.

The driver uses the docker python module to interact with the docker daemon.

For more information on the parameters see:

<https://docker-py.readthedocs.io/en/stable/containers.html#container-objects>

Binds to:**docker_daemon:**

- *DockerDaemon*

Implements:

- *PowerProtocol*

```
DockerDriver:
    image_uri: "rastasheep/ubuntu-sshd:16.04"
    container_name: "ubuntu-lg-example"
    host_config: {"network_mode": "bridge"}
    network_services: [{"port": 22, "username": "root", "password": "root"}]
```

Arguments:

- `image_uri` (str): identifier of the docker image to use (may have a tag suffix)
- `command` (str): command to run in the container (optional, depends on image)
- `volumes` (list): list to configure volumes mounted inside the container (optional)
- `container_name` (str): name of the container
- `environment` (list): list of environment variables (optional)
- `host_config` (dict): dictionary of host configurations
- `network_services` (list): dictionaries that describe individual *NetworkService* instances that come alive when the container is created. The “address” argument which *NetworkService* also requires will be derived automatically upon container creation.

5.2.39 LXAIOPBUSDriver

An LXAIOPBUSDriver binds to a single *LXAIOPBUSDriver* to toggle and read the PIO states.

Binds to:

pio:

- *LXAIOPBUSDriver*
- *NetworkLXAIOPBUSDriver*

```
LXAIOPBUSDriver: {}
```

Implements:

- *DigitalOutputProtocol*

5.2.40 PyVISADriver

The PyVISADriver uses a PyVISADevice resource to control test equipment manageable by PyVISA.

Binds to:

pyvisa_resource:

- *PyVISADevice*

Implements:

- None yet

5.3 Strategies

Strategies are used to ensure that the device is in a certain state during a test. Such a state could be the bootloader or a booted Linux kernel with shell.

5.3.1 BareboxStrategy

A BareboxStrategy has four states:

- unknown

- off
- barebox
- shell

to transition to the shell state:

```
t = get_target("main")
s = BareboxStrategy(t)
s.transition("shell")
```

this command would transition from the bootloader into a Linux shell and activate the shelldriver.

5.3.2 ShellStrategy

A ShellStrategy has three states:

- unknown
- off
- shell

to transition to the shell state:

```
t = get_target("main")
s = ShellStrategy(t)
s.transition("shell")
```

this command would transition directly into a Linux shell and activate the shelldriver.

5.3.3 UBootStrategy

A UBootStrategy has four states:

- unknown
- off
- uboot
- shell

to transition to the shell state:

```
t = get_target("main")
s = UBootStrategy(t)
s.transition("shell")
```

this command would transition from the bootloader into a Linux shell and activate the shelldriver.

5.3.4 DockerShellStrategy

A DockerShellStrategy has three states:

- unknown
- off

- shell

To transition to the shell state:

```
t = get_target("main")
s = DockerShellStrategy(t)
s.transition("shell")
```

These commands would activate the docker driver which creates and starts a docker container. This will subsequently make *NetworkService* instance(s) available which can be used for e.g. SSH access.

Note: Transitioning to the “off” state will make any *NetworkService* instance(s) unresponsive - which may in turn invalidate SSH connection sharing. Therefore, during automated test suites, refrain from transitioning to the “off” state.

5.4 Reporters

5.4.1 StepReporter

The StepReporter outputs individual labgrid steps to *STDOUT*.

```
from labgrid.stepreporter import StepReporter

StepReporter.start()
```

The Reporter can be stopped with a call to the stop function:

```
from labgrid.stepreporter import StepReporter

StepReporter.stop()
```

Stopping the StepReporter if it has not been started will raise an *AssertionError*, as will starting an already started StepReporter.

5.4.2 ColoredStepReporter

The ColoredStepReporter inherits from the StepReporter. The output is colored using ANSI color code sequences.

5.4.3 ConsoleLoggingReporter

The ConsoleLoggingReporter outputs read calls from the console transports into files. It takes the path as a parameter.

```
from labgrid.consoleloggingreporter import ConsoleLoggingReporter

ConsoleLoggingReporter.start(".")
```

The Reporter can be stopped with a call to the stop function:

```
from labgrid.consoleloggingreporter import ConsoleLoggingReporter

ConsoleLoggingReporter.stop()
```

Stopping the ConsoleLoggingReporter if it has not been started will raise an *AssertionError*, as will starting an already started StepReporter.

5.5 Environment Configuration

The environment configuration for a test environment consists of a YAML file which contains targets, drivers and resources. The invocation order of objects is important here since drivers may depend on other drivers or resources.

The skeleton for an environment consists of:

```
targets:
  <target-1>:
    resources:
      <resource-1>:
        <resource-1 parameters>
      <resource-2>:
        <resource-2 parameters>
    drivers:
      <driver-1>:
        <driver-1 parameters>
      <driver-2>: {} # no parameters for driver-2
  <target-2>:
    resources:
      <resources>
    drivers:
      <drivers>
    options:
      <target-option-1-name>: <value for target-option-1>
      <more target-options>
  <more targets>
options:
  <option-1 name>: <value for option-1>
  <more options>
images:
  <image-1 name>: <absolute or relative path for image-1>
  <more images>
tools:
  <tool-1 name>: <absolute or relative path for tool-1>
  <more tools>
imports:
  - <import.py>
  - <python module>
```

If you have a single target in your environment, name it “main”, as the `get_target` function defaults to “main”.

All the resources and drivers in this chapter have a YAML example snippet which can simply be added (at the correct indentation level, one level deeper) to the environment configuration.

If you want to use multiple drivers of the same type, the resources and drivers need to be lists, e.g:

```
resources:
  RawSerialPort:
    port: '/dev/ttyS1'
drivers:
  SerialDriver: {}
```

becomes:

```
resources:
- RawSerialPort:
  port: '/dev/ttyS1'
```

(continues on next page)

(continued from previous page)

```

- RawSerialPort:
  port: '/dev/ttyS2'
drivers:
- SerialDriver: {}
- SerialDriver: {}

```

This configuration doesn't specify which *RawSerialPort* to use for each *SerialDriver*, so it will cause an exception when instantiating the *Target*. To bind the correct driver to the correct resource, explicit name and bindings properties are used:

```

resources:
- RawSerialPort:
  name: 'foo'
  port: '/dev/ttyS1'
- RawSerialPort:
  name: 'bar'
  port: '/dev/ttyS2'
drivers:
- SerialDriver:
  name: 'foo_driver'
  bindings:
  port: 'foo'
- SerialDriver:
  name: 'bar_driver'
  bindings:
  port: 'bar'

```

The property name for the binding (e.g. *port* in the example above) is documented for each individual driver in this chapter.

The YAML configuration file also supports templating for some substitutions, these are:

- LG_* variables, are replaced with their respective LG_* environment variable
- BASE is substituted with the base directory of the YAML file.

As an example:

```

targets:
  main:
    resources:
      RemotePlace:
        name: !template $LG_PLACE
tools:
  qemu_bin: !template "$BASE/bin/qemu-bin"

```

would resolve the *qemu_bin* path relative to the *BASE* dir of the YAML file and try to use the *RemotePlace* with the name set in the *LG_PLACE* environment variable.

See the *labgrid-device-config* man page for documentation on the top-level options, images, tools, and examples keys in the environment configuration.

5.6 Exporter Configuration

The exporter is configured by using a YAML file (with a syntax similar to the environment configs used for pytest) or by instantiating the *Environment* object. To configure the exporter, you need to define one or more *resource groups*,

each containing one or more *resources*. The syntax for exported resource names is `<exporter>/<group>/<class>/<name>`, which allows the exporter to group resources for various usage scenarios, e.g. all resources of a specific place or for a specific test setup. For information on how the exporter fits into the rest of labgrid, see [Remote Resources and Places](#).

The `<exporter>` part can be specified on the `labgrid-exporter` command line, and defaults to the hostname of the exporter.

The basic structure of an exporter configuration file is:

```
<group-1>:
  <resource-name-1>:
    <params>
  <resource-name-2>:
    <params>
<group-2>:
  <resource-name-1>:
    <params>
```

By default, the class name is inferred from the resource name, and `<params>` will be passed to its constructor. For USB resources, you will most likely want to use [udev Matching](#) here.

As a simple example, here is one group called `usb-hub-in-rack12` containing a single `USBSerialPort` resource (using udev matching), which will be exported as `exportername/usb-hub-in-rack12/NetworkSerialPort/USBSerialPort`:

```
usb-hub-in-rack12:
  USBSerialPort:
    match:
      '@sys_name': '3-1.3'
```

To export multiple resources of the same class in the same group, you can choose a unique resource name, and then use the `cls` parameter to specify the class name instead (which will not be passed as a parameter to the class constructor). In this next example we will export one `USBSerialPort` as `exportername/usb-hub-in-rack12/NetworkSerialPort/console-main`, and another `USBSerialPort` as `exportername/usb-hub-in-rack12/NetworkSerialPort/console-secondary`:

```
usb-hub-in-rack12:
  console-main:
    cls: USBSerialPort
    match:
      '@sys_name': '3-1.3'
  console-secondary:
    cls: USBSerialPort
    match:
      '@sys_name': '3-1.4'
```

Note that you could also split the resources up into distinct groups instead to achieve the same effect:

```
usb-hub-in-rack12-port3:
  USBSerialPort:
    match:
      '@sys_name': '3-1.3'
usb-hub-in-rack12-port4:
  USBSerialPort:
    match:
      '@sys_name': '3-1.4'
```

5.6.1 Templating

To reduce the amount of repeated declarations when many similar resources need to be exported, the [Jinja2 template engine](#) is used as a preprocessor for the configuration file:

```
## Iterate from group 1001 to 1016
# for idx in range(1, 17)
{{ 1000 + idx }}:
    NetworkSerialPort:
        {host: rll, port: {{ 4000 + idx }}}
    NetworkPowerPort:
        # if 1 <= idx <= 8
        {model: apc, host: apc1, index: {{ idx }}}
        # elif 9 <= idx <= 12
        {model: netio, host: netio4, index: {{ idx - 8 }}}
        # elif 13 <= idx <= 16
        {model: netio, host: netio5, index: {{ idx - 12 }}}
        # endif
# endfor
```

Use `#` for line statements (like the for loops in the example) and `##` for line comments. Statements like `{{ 4000 + idx }}` are expanded based on variables in the Jinja2 template.

The template processing also supports use of OS environment variables, using something like `{{ env['FOOBAR'] }}` to insert the content of environment variable *FOOBAR*.

DEVELOPMENT

The first step is to install labgrid into a local virtualenv.

6.1 Installation

Clone the git repository:

```
git clone https://github.com/labgrid-project/labgrid && cd labgrid
```

Create and activate a virtualenv for labgrid:

```
virtualenv -p python3 venv  
source venv/bin/activate
```

Install required dependencies:

```
sudo apt install python3-dev libow-dev libsnappy-dev
```

Install the development requirements:

```
pip install -r dev-requirements.txt
```

Install labgrid into the virtualenv in editable mode:

```
pip install -e .
```

Tests can now be run via:

```
python -m pytest --lg-env <config>
```

6.2 Writing a Driver

To develop a new driver for labgrid, you need to decide which protocol to implement, or implement your own protocol. If you are unsure about a new protocol's API, just use the driver directly from the client code, as deciding on a good API will be much easier when another similar driver is added.

labgrid uses the [attrs library](#) for internal classes. First of all import attr, the protocol and the common driver class into your new driver file.

```
import attr

from labgrid.driver.common import Driver
from labgrid.protocol import ConsoleProtocol
```

Next, define your new class and list the protocols as subclasses of the new driver class. Try to avoid subclassing existing other drivers, as this limits the flexibility provided by connecting drivers and resources on a given target at runtime.

```
import attr

from labgrid.driver.common import Driver
from labgrid.protocol import ConsoleProtocol

@attr.s(eq=False)
class ExampleDriver(Driver, ConsoleProtocol):
    pass
```

The ConsoleExpectMixin is a mixin class to add expect functionality to any class supporting the *ConsoleProtocol* and has to be the first item in the subclass list. Using the mixin class allows sharing common code, which would otherwise need to be added into multiple drivers.

```
import attr

from labgrid.driver.common import Driver
from labgrid.driver.consoleexpectmixin import ConsoleExpectMixin
from labgrid.protocol import ConsoleProtocol

@attr.s(eq=False)
class ExampleDriver(ConsoleExpectMixin, Driver, ConsoleProtocol):
    pass
```

Additionally the driver needs to be registered with the *target_factory* and provide a bindings dictionary, so that the *Target* can resolve dependencies on other drivers or resources.

```
import attr

from labgrid.factory import target_factory
from labgrid.driver.common import Driver
from labgrid.driver.consoleexpectmixin import ConsoleExpectMixin
from labgrid.protocol import ConsoleProtocol

@target_factory.reg_driver
@attr.s(eq=False)
class ExampleDriver(ConsoleExpectMixin, Driver, ConsoleProtocol):
    bindings = { "port": SerialPort }
    pass
```

The listed resource `SerialPort` will be bound to `self.port`, making it usable in the class. Checks are performed that the target which the driver binds to has a `SerialPort`, otherwise an error will be raised.

If your driver can support alternative resources, you can use a set of classes instead of a single class:

```
bindings = { "port": {SerialPort, NetworkSerialPort}}
```

Optional bindings can be declared by including `None` in the set:

```
bindings = { "port": {SerialPort, NetworkSerialPort, None}}
```

If you need to do something during instantiation, you need to add a `__attrs_post_init__` method (instead of the usual `__init__` used for non-attr-classes). The minimum requirement is a call to `super().__attrs_post_init__()`.

```
import attr

from labgrid.factory import target_factory
from labgrid.driver.common import Driver
from labgrid.driver.consoleexpectmixin import ConsoleExpectMixin
from labgrid.protocol import ConsoleProtocol

@target_factory.reg_driver
@attr.s(eq=False)
class ExampleDriver(ConsoleExpectMixin, Driver, ConsoleProtocol):
    bindings = { "port": SerialPort }

    def __attrs_post_init__(self):
        super().__attrs_post_init__()
```

All that's left now is to implement the functionality described by the used protocol, by using the API of the bound drivers and resources.

6.3 Writing a Resource

To add a new resource to labgrid, we import `attr` into our new resource file. Additionally we need the `target_factory` and the common Resource class.

```
import attr

from labgrid.factory import target_factory
from labgrid.driver.common import Resource
```

Next we add our own resource with the `Resource` parent class and register it with the `target_factory`.

```
import attr

from labgrid.factory import target_factory
from labgrid.driver.common import Resource

@target_factory.reg_resource
@attr.s(eq=False)
class ExampleResource(Resource):
    pass
```

All that is left now is to add attributes via `attr.ib()` member variables.

```
import attr

from labgrid.factory import target_factory
from labgrid.driver.common import Resource

@target_factory.reg_resource
@attr.s(eq=False)
```

(continues on next page)

(continued from previous page)

```
class ExampleResource(Resource):
    examplevar1 = attr.ib()
    examplevar2 = attr.ib()
```

The `attr.ib()` style of member definition also supports defaults and validators, see the [attrs documentation](#).

6.4 Writing a Strategy

labgrid offers only basic strategies, for complex use cases a customized strategy is required. Start by creating a strategy skeleton:

```
import enum

import attr

from labgrid.step import step
from labgrid.driver import Strategy, StrategyError
from labgrid.factory import target_factory

class Status(enum.Enum):
    unknown = 0

@target_factory.reg_driver
class MyStrategy(Strategy):
    bindings = {
    }

    status = attr.ib(default=Status.unknown)

    @step()
    def transition(self, status, *, step):
        if not isinstance(status, Status):
            status = Status[status]
        if status == Status.unknown:
            raise StrategyError("can not transition to {}".format(status))
        elif status == self.status:
            step.skip("nothing to do")
            return # nothing to do
        else:
            raise StrategyError(
                "no transition found from {} to {}".format(
                    self.status, status
                )
            )
        self.status = status
```

The `bindings` variable needs to declare the drivers necessary for the strategy, usually one for power, bootloader and shell. It is possible to reference drivers via their protocol, e.g. `ConsoleProtocol`. Note that drivers which implement multiple protocols must not be referenced multiple times via different protocols. The `Status` class needs to be extended to cover the states of your strategy, then for each state an `elif` entry in the transition function needs to be added.

Lets take a look at the builtin *BareboxStrategy*. The `Status` enum for the *BareboxStrategy*:

```
class Status(enum.Enum):
    unknown = 0
    off = 1
    barebox = 2
    shell = 3
```

defines 3 custom states and the *unknown* state as the start point. These three states are handled in the transition function:

```
elif status == Status.off:
    self.target.deactivate(self.barebox)
    self.target.deactivate(self.shell)
    self.target.activate(self.power)
    self.power.off()
elif status == Status.barebox:
    self.transition(Status.off)
    # cycle power
    self.power.cycle()
    # interrupt barebox
    self.target.activate(self.barebox)
elif status == Status.shell:
    # transition to barebox
    self.transition(Status.barebox)
    self.barebox.boot("")
    self.barebox.await_boot()
    self.target.activate(self.shell)
```

Here the *barebox* state simply cycles the board and activates the driver, while the *shell* state uses the barebox state to cycle the board and then boot the linux kernel. The *off* states switch the power off.

6.5 Tips for Writing and Debugging Tests

6.5.1 Live-Reading Console Output

When starting labgrid with `--lg-log` option, it will dump the input from the serial driver to a file in specified directory:

```
$ pytest .. --lg-log=logdir test-dir/
```

This can help understanding what happened and why it happened. However, when debugging tests, it might be more helpful to get a live impression of what is going on. For this, you can use `tail -f` to read the content written to the log file as if you would be connected to the devices serial console (except that it is read-only):

```
$ tail -f logdir/console_main # for the 'main' target
```

For getting information about timing, the `annotate-output` command turned out to be quite helpful. On Debian it comes with the `devscripts` package and you can install it with:

```
$ apt-get install devscripts
```

To use it, run:

```
$ annotate-output tail -f logdir/console_main
```

This will print your system time before each line, allowing you to both see relative delays between steps in your tests as well as absolute timing of things happening in your test environment.

6.5.2 Dealing With Kernel Log Verbosity

For testing your Linux system it can be quite annoying if the kernel outputs verbosely to the console you use for testing. Note that a too verbose kernel can break tests as kernel logs will pollute the expected command outputs making it unreadable for labgrid regular expressions.

However, as the shell driver and most of the tests will depend on seeing console output of what is going on during boot, we cannot turn off kernel logging completely.

Note: The labgrid ShellDriver itself attempts to disable console printing by calling `dmesg -n 1` as soon as having a logged-in shell. However, this may be too late for reliably capturing the initial login and shell prompt.

A proper point in time for disabling kernel output to the console is when systemd starts. To achieve this, make use of the `systemd-sysctl.service` that uses `/etc/sysctl.d/` to configure kernel parameters. This way, the kernel log level can be set to ‘error’ by the time of service execution with a config file like:

```
$ cat /etc/sysctl.d/20-quiet-printk.conf
kernel.printk = 3
```

If the *initial* kernel logging is still too high, one could also reduce this. But note that for the standard configuration of the labgrid barebox and uboot drivers, we need to catch the `Linux version . . .` line to detect we successfully left the bootloader (the `bootstring` attribute). This line is only printed when having at least kernel log level 6 (notice) enabled:

```
loglevel=6
```

6.6 Graph Strategies

Warning: This feature is experimental and brings much complexity to your project.

GraphStrategies are made for more complex strategies, with multiple, on each other depending, states. A GraphStrategy graph has to be a directed graph with one root state.

Using a GraphStrategy makes only sense if you have board states that are reachable by different ways. In this case GraphStrategies reduce state duplication.

6.6.1 Example

Listing 1: conftest.py

```
from labgrid.strategy import GraphStrategy

class TestStrategy(GraphStrategy):
    def state_unknown(self):
        pass
```

(continues on next page)

(continued from previous page)

```

@GraphStrategy.depends('unknown')
def state_boot_via_nand(self):
    pass

@GraphStrategy.depends('unknown')
def state_boot_via_nfs(self):
    pass

@GraphStrategy.depends('boot_via_nand', 'boot_via_nfs')
def state_barebox(self):
    pass

@GraphStrategy.depends('barebox')
def state_linux_shell(self):
    pass

```

The class can also render a graph as PNG (using GraphViz):

Listing 2: test.yaml

```

targets:
  main:
    resources: {}
    drivers: {}

```

Listing 3: render_teststrategy.py

```

from labgrid.environment import Environment
from conftest import TestStrategy
env = Environment('test.yaml')
strategy = TestStrategy(env.get_target(), "strategy name")

strategy.transition('barebox', via=['boot_via_nfs'])
# returned: ['unknown', 'boot_via_nfs', 'barebox']
strategy.graph.render("teststrategy-via-nfs")
# returned: 'teststrategy-via-nfs.png'

strategy.transition('barebox', via=['boot_via_nand'])
# returned: ['unknown', 'boot_via_nand', 'barebox']
strategy.graph.render("teststrategy-via-nand")
# returned: 'teststrategy-via-nand.png'

```

6.6.2 State

Every graph node describes a board state and how to reach it, A state has to be a class method following this prototype:
`def state_${STATENAME}(self) :` A state may not call `transition()` in its state definition.

6.6.3 Dependency

Every state, but the root state, can depend on other States, If a state has multiple dependencies, not all of them, but one, have to be reached before running the current state. When no via is used during a transition the order of the given dependencies decides which one gets called, where the first one has the highest priority and the last one the lowest. Dependencies are represented by graph edges.




Fig. 1: TestStrategy transitioned to 'barebox' via 'boot_via_nfs'




Fig. 2: TestStrategy transitioned to 'barebox' via 'boot_via_nand'

6.6.4 Root State

Every GraphStrategy has to define exactly one root state. The root state defines the start of the graph and therefore the start of every transition. A state becomes a root state if it has no dependencies.

6.6.5 Transition

A transition describes a path, or a part of a path, through a GraphStrategy graph. Every State in the graph has a auto generated default path starting from the root state. So using the given example, the GraphStrategy would call the states *unknown*, *boot_via_nand*, *barebox*, and *linux_shell* in this order if `transition('linux_shell')` would be called. The GraphStrategy would prefer *boot_via_nand* over *boot_via_nfs* because *boot_via_nand* is mentioned before *boot_via_nfs* in the dependencies of *barebox*. If you want to reach via *boot_via_nfs* the call would look like this: `transition('linux_shell', via='boot_via_nfs')`.

A transition can be incremental. If we trigger a transition with `transition('barebox')` first, the states *unknown*, *boot_via_nand* and *barebox* will be called in this order. If we trigger a transition `transition('linux_shell')` afterwards only *linux_shell* gets called. This happens because *linux_shell* is reachable from *barebox* and the Strategy holds state of the last walked path. But there is a catch! The second, incremental path must be *fully* incremental to the previous path! For example: Lets say we reached *barebox* via *boot_via_nfs*, (`transition('barebox', via='boot_via_nfs')`). If we trigger `transition('linux_shell')` afterwards the GraphStrategy would compare the last path '*unknown*', '*boot_via_nfs*', '*barebox*' with the default path to *linux_shell* which would be '*unknown*', '*boot_via_nand*', '*barebox*', '*linux_shell*', and decides the path is not fully incremental and starts over by the root state. If we had given the second transition *boot_via_nfs* like in the first transition the paths had been incremental.

6.7 SSHManager

labgrid provides a SSHManager to allow connection reuse with control sockets. To use the SSHManager in your code, import it from `labgrid.util.ssh`:

```
from labgrid.util.ssh import sshmanager
```

you can now request or remove forwards:

```
from labgrid.util.ssh import sshmanager

localport = sshmanager.request_forward('somehost', 3000)

sshmanager.remove_forward('somehost', 3000)
```

or get and put files:

```
from labgrid.util.ssh import sshmanager

sshmanager.put_file('somehost', '/path/to/local/file', '/path/to/remote/file')
```

Note: The SSHManager will reuse existing Control Sockets and set up a keepalive loop to prevent timeouts of the socket during tests.

6.8 ManagedFile

While the *SSHManager* exposes a lower level interface to use SSH Connections, the *ManagedFile* provides a higher level interface for file upload to another host. It is meant to be used in conjunction with a remote resource, and store the file on the remote host with the following pattern:

```
/tmp/labgrid-<username>/<sha256sum>/<filename>
```

Additionally it provides *get_remote_path()* to retrieve the complete file path, to easily employ it for driver implementations. To use it in conjunction with a *Resource* and a file:

```
from labgrid.util.managedfile import ManagedFile

mf = ManagedFile(<your-file>, <your-resource>)
mf.sync_to_resource()
path = mf.get_remote_path()
```

Unless constructed with *ManagedFile(..., detect_nfs=False)*, *ManagedFile* employs the following heuristic to check if a file is stored on a NFS share available both locally and remotely via the same path:

- check if GNU coreutils *stat(1)* with option *-format* exists on local and remote system
- check if inode number, total size and birth/modification timestamps match on local and remote system

If this is the case the actual file transfer in *sync_to_resource* is skipped.

6.9 ProxyManager

The proxymanager is used to open connections across proxies via an attribute in the resource. This allows gated testing networks by always using the exporter as an SSH gateway to proxy the connections using SSH Forwarding. Currently this is used in the *SerialDriver* for proxy connections.

Usage:

```
from labgrid.util.proxy import proxymanager

proxymanager.get_host_and_port(<resource>)
```

6.10 Contributing

Thank you for thinking about contributing to labgrid! Some different backgrounds and use-cases are essential for making labgrid work well for all users.

The following should help you with submitting your changes, but don't let these guidelines keep you from opening a pull request. If in doubt, we'd prefer to see the code earlier as a work-in-progress PR and help you with the submission process.

6.10.1 Workflow

- Changes should be submitted via a [GitHub pull request](#).
- Try to limit each commit to a single conceptual change.

- Add a signed-off-by line to your commits according to the *Developer's Certificate of Origin* (see below).
- Check that the tests still work before submitting the pull request. Also check the CI's feedback on the pull request after submission.
- When adding new drivers or resources, please also add the corresponding documentation and test code.
- If your change affects backward compatibility, describe the necessary changes in the commit message and update the examples where needed.

6.10.2 Code

- Follow the [PEP 8](#) style.
- Use `attr.ib` attributes for public attributes of your drivers and resources.
- Use `isort` to sort the import statements.

6.10.3 Documentation

- Use [semantic linefeeds](#) in `.rst` files.

6.10.4 Run Tests

```
$ tox -r
```

6.10.5 Developer's Certificate of Origin

labgrid uses the [Developer's Certificate of Origin 1.1](#) with the same [process](#) as used for the Linux kernel:

Developer's Certificate of Origin 1.1

By making a contribution to this project, I certify that:

- (a) The contribution was created in whole or in part by me and I have the right to submit it under the open source license indicated in the file; or
- (b) The contribution is based upon previous work that, to the best of my knowledge, is covered under an appropriate open source license and I have the right under that license to submit that work with modifications, whether created in whole or in part by me, under the same open source license (unless I am permitted to submit under a different license), as indicated in the file; or
- (c) The contribution was provided directly to me by some other person who certified (a), (b) or (c) and I have not modified it.
- (d) I understand and agree that this project and the contribution are public and that a record of the contribution (including all personal information I submit with it, including my sign-off) is maintained indefinitely and may be redistributed consistent with this project or the open source license(s) involved.

Then you just add a line (using `git commit -s`) saying:

Signed-off-by: Random J Developer <random@developer.example.org>

using your real name (sorry, no pseudonyms or anonymous contributions).

6.11 Ideas

6.11.1 Driver Preemption

To allow better handling of unexpected reboots or crashes, inactive Drivers could register callbacks on their providers (for example the BareboxDriver it's ConsoleProtocol). These callbacks would look for indications that the Target has changed state unexpectedly (by looking for the bootloader startup messages, in this case). The inactive Driver could then cause a preemption and would be activated. The current caller of the originally active driver would be notified via an exception.

6.11.2 Step Tracing

The Step infrastructure already collects timing and nesting information on executed commands, but is currently only used in the pytest plugin or via the standalone StepReporter. By writing these events to a file (or sqlite database) as a trace, we can collect data over multiple runs for later analysis. This would become more useful by passing recognized events (stack traces, crashes, ...) and benchmark results via the Step infrastructure.

6.11.3 CommandProtocol Support for Background Processes

Currently the CommandProtocol does not support long running processes well. An implementation should start a new process, return a handle and forbid running other processes in the foreground. The handle can be used to retrieve output from a command.

DESIGN DECISIONS

This document outlines the design decisions influencing the development of labgrid.

7.1 Out of Scope

Out of scope for labgrid are:

7.1.1 Integrated Build System

In contrast to some other tools, labgrid explicitly has no support for building target binaries or images.

Our reasons for this are:

- Several full-featured build systems already exist and work well.
- We want to test unmodified images produced by any build system (OE/Yocto, PTXdist, Buildroot, Debian, ...).

7.1.2 Test Infrastructure

labgrid does not include a test framework.

The main reason is that with `pytest` we already have a test framework which:

- makes it easy to write tests
- reduces boilerplate code with flexible fixtures
- is easy to extend and has many available plugins
- allows using any Python library for creating inputs or processing outputs
- supports test report generation

Furthermore, the hardware control functionality needed for testing is also very useful during development, provisioning and other areas, so we don't want to hide that behind another test framework.

7.2 In Scope

- usable as a library for hardware provisioning
- device control via:
 - serial console

- SSH
 - file management
 - power and reset
- emulation of external services:
 - USB stick emulation
 - external update services (Hawkbitt)
- bootstrap services:
 - fastboot
 - imxusbloader

7.3 Further Goals

- tests should be equivalent for workstations and servers
- discoverability of available boards
- distributed board access

CHANGES

8.1 Release 0.3.4 (released Apr 1, 2021)

8.2 Bug Fixes in 0.3.4

- Fix inclusion of the README file to support PyPi Uploads

8.3 Release 0.3.3 (released Apr 1, 2021)

8.4 Bug Fixes in 0.3.3

- limit twisted version within crossbar-requirements.txt
- the EthernetPort and SerialPort resources now properly raise their exceptions instead of only creating them
- fixed docker cryptography failure during build
- remove ports configuration from docker-compose.yml
- add rsync to docker-client image

8.4.1 Known issues in 0.3.3

- There are several reports of `sshpass` used within the `SSHDriver` not working in all cases or only on the first connection.
- Some client commands return 0 even if the command failed.
- Currently empty passwords are not well supported by the `ShellDriver`

8.5 Release 0.3.2 (released Mar 14, 2021)

8.6 Bug Fixes in 0.3.2

- Fix for exporter baud rate handling which prevented `ser2net` from starting.

8.6.1 Known issues in 0.3.2

- There are several reports of `sshpas` used within the `SSHDriver` not working in all cases or only on the first connection.
- Some client commands return 0 even if the command failed.
- Currently empty passwords are not well supported by the `ShellDriver`

8.7 Release 0.3.1 (released Feb 5, 2021)

8.8 Bug Fixes in 0.3.1

- Fixes a typo in `labgrid-bound-connect`, which should re-enable connection proxying for SSH.
- Man-Pages have been correctly regenerated.
- The exporter correctly handles the configured baud-rate for serial ports again.
- Various tests have been marked with skips if the modules are not available.
- Docker files have been moved to from the `docker` directory to the `dockerfiles` directory, which prevents the tests from incorrectly assuming a docker module is available.

8.9 Release 0.3.0 (released Jan 22, 2021)

8.9.1 New Features in 0.3.0

- All *CommandProtocol* drivers support the `poll_until_success` method.
- The new *FileDigitalOutputDriver* represents a digital signal with a file.
- The new *GpioDigitalOutputDriver* controls the state of a GPIO via the `sysfs` interface.
- Crossbar and autobahn have been updated to 19.3.3 and 19.3.5 respectively.
- The `InfoDriver` was removed. The functions have been integrated into the `labgridhelper` library, please use the library for the old functionality.
- `labgrid-client write-image` subcommand: `labgrid` client now has a `write-image` command to write images onto block devices.
- `labgrid-client ssh` now also uses port from `NetworkService` resource if available
- The `PLACE` and `STATE` variables used by `labgrid-client` are replaced by `LG_PLACE` and `LG_STATE`, the old variables are still supported for the time being.
- The `SSHDriver`'s `keyfile` attribute is now specified relative to the config file just like the images are.
- The `ShellDriver`'s `keyfile` attribute is now specified relative to the config file just like the images are.
- `labgrid-client -P <PROXY>` and the `LG_PROXY` environment variable can be used to access the coordinator and network resources via that SSH proxy host. Drivers which run commands via SSH to the exporter still connect directly, allowing custom configuration in the user's `.ssh/config` as needed. Note that not all drivers have been updated to use the `ProxyManager` yet.
- Deditec RELAIS8 devices are now supported by the *DeditecRelaisDriver*.

- The *RKUSBDriver* was added to support the rockchip serial download mode.
- The *USBStorageDriver* gained support for BMAP.
- Flashrom support added, by hard-wiring e.g. an exporter to the DUT, the ROM on the DUT can be written directly. The flashrom driver implements the bootstrap protocol.
- AndroidFastbootDriver now supports 'getvar' and 'oem getenv' subcommands.
- The coordinator now updates the resource acquired state at the exporter. Accordingly, the exporter now starts ser2net only when a resources is aquired. Furthermore, resource conflicts between places are now detected.
- Labgrid now uses the *ProcessWrapper* for externally called processes. This should include output from these calls better inside the test runs.
- The binding dictionary can now supports type name strings in addition to the types themselves, avoiding the need to import a specific protocol or driver in some cases.
- The remote infrastructure gained support for place reservations, for further information check the section in the documentation.
- The *SigrokDriver* gained support for the Manson HCS-2302, it allows enabling and disabling channels, measurement and setting the current and voltage limit.
- `labgrid-client write-image` gained new arguments: `--partition`, `--skip`, `--seek`.
- Support for Sentry PDUs has been added.
- Strategies now implement a `force` method, to force a strategy state irrespective of the current state.
- SSH Connections can now be proxied over the exporter, used by adding a device suffix to the *NetworkService* address.
- UBootDriver now allows overriding of default boot command (`run bootcmd`) via new `boot_command` argument.
- The config file supports per-target options, in addition to global options.
- Add power driver to support GEMBIRD SiS-PM implementing *SiSPMPowerDriver*.
- A cleanup of the cleanup functions was performed, labgrid should now clean up after itself and throws an error if the user needs to handle it himself.
- `labgrid-client` now respects the `LG_HOSTNAME` and `LG_USERNAME` environment variables to set the hostname and username when accessing resources.
- PyVISA support added, allowing to use PyVISA controlled test equipment from Labgrid.
- `labgrid-client write-image` gained a new argument `--mode` to specify which tool should be used to write the image (either `dd` or `bmaptool`)
- Exporter configuration file `exporter.yaml` now allows use of environment variables.

8.9.2 Breaking changes in 0.3.0

- *ManagedFile* now saves the files in a different directory on the exporter. Previously `/tmp` was used, labgrid now uses `/var/cache/labgrid`. A `tmpfiles` example configuration for systemd is provided in the `/contrib` directory. It is also highly recommended to enable `fs.protected_regular=1` and `fs.protected_fifos=1` for kernels ≥ 4.19 . This requires user intervention after the upgrade to create the directory and setup the cleanup job.
- `@attr.s(cmp=False)` is deprecated and all classes have been moved to `@attr.s(eq=False)`, this release requires attrs version 19.2.0

- Coordinator work dir is now set to the same dir as the crossbar configuration dir. Hence coordinator specific files like `places.yaml` and `resources.yaml` are now also stored in the crossbar configuration folder. Previously it would use ...
- The `HawkbittestClient` and `USBstick` classes have been removed
- The original `USBStorageDriver` was removed, `NetworkUSBStorageDriver` was renamed to `USBStorageDriver`. A deprecated `NetworkUSBStorageDriver` exists temporarily for compatibility reasons.

8.9.3 Known issues in 0.3.0

- There are several reports of `sshpas` used within the `SSHDriver` not working in all cases or only on the first connection.
- Some client commands return 0 even if the command failed.
- Currently empty passwords are not well supported by the `ShellDriver`

8.10 Release 0.2.0 (released Jan 4, 2019)

8.10.1 New Features in 0.2.0

- A colored `StepReporter` was added and can be used with `pytest --lg-colored-steps`.
- `labgrid-client` can now use the last changed information to sort listed resources and places.
- `labgrid-client ssh` now uses `ip/user/password` from `NetworkService` resource if available
- The `pytest` plugin option `--lg-log` enables logging of the serial traffic into a file (see below).
- The environment files can contain feature flags which can be used to control which tests are run in `pytest`.
- `LG_*` variables from the OS environment can be used in the config file with the `!template` directive.
- The new “managed file” support takes a local file and synchronizes it to a resource on a remote host. If the resource is not a `NetworkResource`, the local file is used instead.
- `ProxyManager`: a class to automatically create `ssh` forwardings to proxy connections over the exporter
- `SSHManager`: a global manager to multiplex connections to different exporters
- The target now saves it’s attached drivers, resources and protocols in a lookup table, avoiding the need of importing many `Drivers` and `Protocols` (see *Syntactic sugar for Targets*)
- When multiple `Drivers` implement the same `Protocol`, the best one can be selected using a priority (see below).
- The new subcommand `labgrid-client monitor` shows resource or places changes as they happen, which is useful during development or debugging.
- The environment `yaml` file can now list Python files (under the ‘imports’ key). They are imported before constructing the `Targets`, which simplifies using custom `Resources`, `Drivers` or `Strategies`.
- The `pytest` plugin now stores metadata about the environment `yaml` file in the junit XML output.
- The `labgrid-client` tool now understands a `--state` option to transition to the provided state using a `Strategy`. This requires an environment `yaml` file with a `RemotePlace` `Resources` and matching `Drivers`.
- Resource matches for places configured in the coordinator can now have a name, allowing multiple resources with the same class.

- The new `Target.__getitem__` method makes writing using protocols less verbose.
- Experimental: The labgrid-autoinstall tool was added (see below).

8.10.2 New and Updated Drivers

- The new `DigitalOutputResetDriver` adapts a driver implementing the `DigitalOutputProtocol` to the `ResetProtocol`.
- The new `ModbusCoilDriver` support outputs on a ModbusTCP device.
- The new `NetworkUSBStorageDriver` allows writing to remote USB storage devices (such as SD cards or memory sticks connected to a mux).
- The new `QEMUDriver` runs a system image in QEmu and implements the `ConsoleProtocol` and `PowerProtocol`. This allows using labgrid without any real hardware.
- The new `QuartusHPSDriver` controls the “Quartus Prime Programmer and Tools” to flash a target’s QSPI.
- The new `SerialPortDigitalOutputDriver` controls the state of a GPIO using the control lines of a serial port.
- The new `SigrokDriver` uses a (local or remote) device supported by sigrok to record samples.
- The new `SmallUBootDriver` supports the extremely limited U-Boot found in cheap WiFi routers.
- The new `USBSDMuxDriver` controls a Pengutronix USB-SD-Mux device.
- The new `USBTMCDriver` can fetch measurements and screenshots from the “Keysight DSOX2000 series” and the “Tektronix TDS 2000 series”.
- The new `USBVideoDriver` can stream video from a remote H.264 UVC (USB Video Class) camera using gstreamer over SSH. Currently, configuration for the “Logitech HD Pro Webcam C920” exists.
- The new `XenaDriver` allows interacting with Xena network testing equipment.
- The new `YKUSHPowerDriver` and `USBPowerDriver` support software-controlled USB hubs.
- The bootloader drivers now have a `reset` method.
- The `BareboxDriver`’s boot string is now configurable, which allows it to work with the `quiet` Linux boot parameter.
- The `IMXUSBLoader` now recognizes more USB IDs.
- The `OpenOCDDriver` is now more flexible with loading configuration files.
- The `NetworkPowerDriver` now additionally supports:
 - 24 port “Gude Expert Power Control 8080”
 - 8 port “Gude Expert Power Control 8316”
 - NETIO 4 models (via telnet)
 - a simple REST interface
- The `SerialDriver` now supports using plain TCP instead of RFC 2217, which is needed from some console servers.
- The `ShellDriver` has been improved:
 - It supports configuring the various timeouts used during the login process.
 - It can use xmodem to transfer file from and to the target.

8.10.3 Incompatible Changes

- When using the coordinator, it must be upgrade together with the clients because of the newly introduce match names.
- Resources and Drivers now need to be created with an explicit name parameter. It can be `None` to keep the old behaviour. See below for details.
- Classes derived from `Resource` or `Driver` now need to use `@attr.s(cmp=False)` instead of `@attr.s` because of a change in the `attrs` module version 17.1.0.

8.10.4 Syntactic sugar for Targets

Targets are now able to retrieve requested drivers, resources or protocols by name instead of by class. This allows removing many imports, e.g.

```
from labgrid.driver import ShellDriver

shell = target.get_driver(ShellDriver)
```

becomes

```
shell = target.get_driver("ShellDriver")
```

Also take a look at the examples, they have been ported to the new syntax as well.

8.10.5 Multiple Driver Instances

For some Protocols, it is useful to allow multiple instances.

DigitalOutputProtocol: A board may have two jumpers to control the boot mode in addition to a reset GPIO. Previously, it was not possible to use these on a single target.

ConsoleProtocol: Some boards have multiple console interfaces or expose a login prompt via a USB serial gadget.

PowerProtocol: In some cases, multiple power ports need to be controlled for one Target.

To support these use cases, Resources and Drivers must be created with a name parameter. When updating your code to this version, you can either simply set the name to `None` to keep the previous behaviour. Alternatively, pass a string as the name.

Old:

```
>>> t = Target("MyTarget")
>>> SerialPort(t)
SerialPort(target=Target(name='MyTarget', env=None), state=<BindingState.bound: 1>,
↳avail=True, port=None, speed=115200)
>>> SerialDriver(t)
SerialDriver(target=Target(name='MyTarget', env=None), state=<BindingState.bound: 1>,
↳txdelay=0.0)
```

New (with name=None):

```
>>> t = Target("MyTarget")
>>> SerialPort(t, None)
SerialPort(target=Target(name='MyTarget', env=None), name=None, state=<BindingState.
↳bound: 1>, avail=True, port=None, speed=115200)
```

(continues on next page)

(continued from previous page)

```
>>> SerialDriver(t, None)
SerialDriver(target=Target(name='MyTarget', env=None), name=None, state=<BindingState.
↳bound: 1>, txdelay=0.0)
```

New (with real names):

```
>>> t = Target("MyTarget")
>>> SerialPort(t, "MyPort")
SerialPort(target=Target(name='MyTarget', env=None), name='MyPort', state=
↳<BindingState.bound: 1>, avail=True, port=None, speed=115200)
>>> SerialDriver(t, "MyDriver")
SerialDriver(target=Target(name='MyTarget', env=None), name='MyDriver', state=
↳<BindingState.bound: 1>, txdelay=0.0)
```

8.10.6 Priorities

Each driver supports a priorities class variable. This allows drivers which implement the same protocol to add a priority option to each of their protocols. This way a [NetworkPowerDriver](#) can implement the [ResetProtocol](#), but if another [ResetProtocol](#) driver with a higher protocol is available, it will be selected instead. See the documentation for details.

8.10.7 ConsoleLogging Reporter

The ConsoleLoggingReporter can be used with the pytest plugin or the library. It records the Data send from a DUT to the computer running labgrid. The logfile contains a header with the name of the device from the environment configuration and a timestamp.

When using the library, the reporter can be started with:

```
from labgrid.consoleloggingreporter import ConsoleLoggingReporter

ConsoleLoggingReporter.start(".")
```

where “.” is the output directory.

The pytest plugin accepts the `--lg-log` commandline option, either with or without an output path.

8.10.8 Auto-Installer Tool

To simplify using labgrid for provisioning several boards in parallel, the `labgrid-autoinstall` tool was added. It reads a YAML file defining several targets and a Python script to be run for each board. Internally, it spawns a child process for each target, which waits until a matching resource becomes available and then executes the script.

For example, this makes it simple to load a bootloader via the [BootstrapProtocol](#), use the [AndroidFastbootDriver](#) to upload a kernel with `initramfs` and then write the target's eMMC over a USB Mass Storage gadget.

Note: `labgrid-autoinstall` is still experimental and no documentation has been written.

Contributions from: Ahmad Fatoum, Bastian Krause, Björn Lässig, Chris Fiege, Enrico Joerns, Esben Haabendal, Felix Lampe, Florian Scherf, Georg Hofmann, Jan Lübke, Jan Remmet, Johannes Nau, Kasper Revsbech, Kjeld

Flarup, Laurentiu Palcu, Oleksij Rempel, Roland Hieber, Rouven Czerwinski, Stanley Phoong Cheong Kwan, Steffen Trumtrar, Tobi Gschwendtner, Vincent Prince

8.11 Release 0.1.0 (released May 11, 2017)

This is the initial release of labgrid.

MODULES

9.1 labgrid package

9.1.1 Subpackages

labgrid.autoinstall package

Submodules

labgrid.autoinstall.main module

The autoinstall.main module runs an installation script automatically on multiple targets.

class labgrid.autoinstall.main.**Handler** (*env, args, name*)

Bases: multiprocessing.context.Process

__init__ (*env, args, name*)

Initialize self. See help(type(self)) for accurate signature.

run ()

Method to be run in sub-process; can be overridden in sub-class

run_once ()

__module__ = 'labgrid.autoinstall.main'

class labgrid.autoinstall.main.**Manager** (*env, args*)

Bases: object

__init__ (*env, args*)

Initialize self. See help(type(self)) for accurate signature.

configure ()

start ()

join ()

__dict__ = mappingproxy({'__module__': 'labgrid.autoinstall.main', '__init__': <func

__module__ = 'labgrid.autoinstall.main'

__weakref__

list of weak references to the object (if defined)

labgrid.autoinstall.main.**main** ()

labgrid.driver package

Subpackages

labgrid.driver.power package

Submodules

labgrid.driver.power.apc module

labgrid.driver.power.apc.**power_set** (*host, port, index, value*)

labgrid.driver.power.apc.**power_get** (*host, port, index*)

labgrid.driver.power.digipower module

labgrid.driver.power.digipower.**power_set** (*host, port, index, value*)

labgrid.driver.power.digipower.**power_get** (*host, port, index*)

labgrid.driver.power.gude module

labgrid.driver.power.gude.**power_set** (*host, port, index, value*)

labgrid.driver.power.gude.**power_get** (*host, port, index*)

labgrid.driver.power.gude24 module

This driver implements a power port for Gude Power Switches with up to 24 ports. These switches differ in their API to the previous 8-port switches for set- and get-commands.

Driver has been tested with: * Gude Expert Power Control 8080

labgrid.driver.power.gude24.**power_set** (*host, port, index, value*)

The gude web-interface uses different pages for the three groups of switches. The web-interface always uses the 'correct' page to set a value. But commands for all pages are accepted on all pages.

labgrid.driver.power.gude24.**power_get** (*host, port, index*)

Get the status of a port.

labgrid.driver.power.gude24.**get_state** (*request, index*)

The status of the ports is made available via a html <meta>-tag using the following format: <meta http-equiv="powerstate" content="Power Port 1,0"> Again the status of all ports is made available on all pages.

labgrid.driver.power.gude8031 module

labgrid.driver.power.gude8031.**power_set** (*host, port, index, value*)

labgrid.driver.power.gude8031.**power_get** (*host, port, index*)

labgrid.driver.power.gude8316 module

labgrid.driver.power.gude8316.**power_set** (*host, port, index, value*)

labgrid.driver.power.gude8316.**power_get** (*host, port, index*)

labgrid.driver.power.netio module

labgrid.driver.power.netio.**power_set** (*host, port, index, value*)

labgrid.driver.power.netio.**power_get** (*host, port, index*)

labgrid.driver.power.netio_kshell module

tested with NETIO 4C, should be compatible with all NETIO 4-models

labgrid.driver.power.netio_kshell.**power_set** (*host, port, index, value*)

labgrid.driver.power.netio_kshell.**power_get** (*host, port, index*)

labgrid.driver.power.sentry module

This driver was tested on those models: CW-24VDD and 4805-XLS-16 but should be working on all devices implementing Sentry3-MIB

labgrid.driver.power.sentry.**power_set** (*host, port, index, value*)

labgrid.driver.power.sentry.**power_get** (*host, port, index*)

labgrid.driver.power.simplerest module

Simple rest interface for Power Port. Used for ex. misc Raspberry Pi configs Author: Kjeld Flarup
<kfa@deif.com>

The URL given in hosts in exporter.yaml must replace {value} with '0' or '1' It is optional whether to use {index} or not.

NetworkPowerPort: model: simplerest host: 'http://172.17.180.53:9999/relay/{index}/{value}' index: 0

labgrid.driver.power.simplerest.**power_set** (*host, port, index, value*)

labgrid.driver.power.simplerest.**power_get** (*host, port, index*)

labgrid.driver.usbtmc package

Submodules

labgrid.driver.usbtmc.keysight_dsox2000 module

labgrid.driver.usbtmc.keysight_dsox2000.**get_channel_info** (*driver, channel*)

labgrid.driver.usbtmc.keysight_dsox2000.**get_channel_values** (*driver, channel*)

labgrid.driver.usbtmc.keysight_dsox2000.**get_screenshot_png** (*driver*)

labgrid.driver.usbtmc.tektronix_tds2000 module

`labgrid.driver.usbtmc.tektronix_tds2000.get_channel_info(driver, channel)`

`labgrid.driver.usbtmc.tektronix_tds2000.get_channel_values(driver, channel)`

`labgrid.driver.usbtmc.tektronix_tds2000.get_screenshot_tiff(driver)`

Submodules

labgrid.driver.bareboxdriver module

```
class labgrid.driver.bareboxdriver.BareboxDriver(target, name, prompt="", auto-
                                                boot='stop autoboot', interrupt='n',
                                                bootstring='Linux version \d',
                                                password="", login_timeout=60)

Bases:      labgrid.driver.commandmixin.CommandMixin, labgrid.driver.common.
            Driver, labgrid.protocol.commandprotocol.CommandProtocol, labgrid.protocol.
            linuxbootprotocol.LinuxBootProtocol
```

BareboxDriver - Driver to control barebox via the console. BareboxDriver binds on top of a ConsoleProtocol.

Parameters

- **prompt** (*str*) – The default Barebox Prompt
- **bootstring** (*str*) – string that indicates that the Kernel is booting
- **password** (*str*) – optional, password to use for access to the shell
- **login_timeout** (*int*) – optional, timeout for access to the shell

```
bindings = {'console': <class 'labgrid.protocol.consoleprotocol.ConsoleProtocol'>}
```

```
__attrs_post_init__ ()
```

```
on_activate ()
```

Activate the BareboxDriver

This function tries to login if not already active

```
on_deactivate ()
```

Deactivate the BareboxDriver

Simply sets the internal status to 0

```
run (cmd: str, *, timeout: int = 30)
```

Run a command

```
reset ()
```

Reset the board via a CPU reset

```
get_status ()
```

Retrieve status of the BareboxDriver 0 means inactive, 1 means active.

Returns status of the driver

Return type int

await_boot()

Wait for the initial Linux version string to verify we successfully jumped into the kernel.

boot(name: str)

Boot the default or a specific boot entry

Parameters **name** (*str*) – name of the entry to boot

__abstractmethods__ = frozenset({})

__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True

__init__(target, name, prompt=", autoboot='stop autoboot', interrupt='\n', bootstring='Linux version \d', password=", login_timeout=60) → None

Method generated by attrs for class BareboxDriver.

__module__ = 'labgrid.driver.bareboxdriver'

__repr__()

Method generated by attrs for class BareboxDriver.

labgrid.driver.commandmixin module

class labgrid.driver.commandmixin.CommandMixin

Bases: object

CommandMixin implementing common functions for drivers which support the CommandProtocol

__attrs_post_init__()

wait_for(cmd, pattern, timeout=30.0, sleepduration=1)

Wait until the pattern is detected in the output of cmd. Raises ExecutionError when the timeout expires.

Parameters

- **cmd** (*str*) – command to run on the shell
- **pattern** (*str*) – pattern as a string to look for in the output
- **timeout** (*float*) – timeout for the pattern detection
- **sleepduration** (*int*) – sleep time between the runs of the cmd

poll_until_success(cmd, *, expected=0, tries=None, timeout=30.0, sleepduration=1)

Poll a command until a specific exit code is detected. Takes a timeout and the number of tries to run the cmd. The sleepduration argument sets the duration between runs of the cmd.

Parameters

- **cmd** (*str*) – command to run on the shell
- **expected** (*int*) – exitcode to detect
- **tries** (*int*) – number of tries, can be None for infinite tries
- **timeout** (*float*) – timeout for the exitcode detection
- **sleepduration** (*int*) – sleep time between the runs of the cmd

Returns whether the command finally executed successfully

Return type bool

run_check(cmd: str, *, timeout=30, codec='utf-8', decodeerrors='strict')

External run_check function, only available if the driver is active. Runs the supplied command and returns the stdout, raises an ExecutionError otherwise.

Parameters `cmd` (*str*) – command to run on the shell

Returns stdout of the executed command

Return type List[str]

```
__dict__ = mappingproxy({'__module__': 'labgrid.driver.commandmixin', '__doc__': '\n__module__ = 'labgrid.driver.commandmixin'\n__weakref__\nlist of weak references to the object (if defined)
```

labgrid.driver.common module

class labgrid.driver.common.**Driver** (*target, name*)

Bases: *labgrid.binding.BindingMixin*

Represents a driver which is used externally or by other drivers. It implements functionality based on directly accessing the Resource or by building on top of other Drivers.

Life cycle: - create - bind (n times) - activate - usage - deactivate

```
__attrs_post_init__()
```

get_priority (*protocol*)

Retrieve the priority for a given protocol

Arguments: protocol - protocol to search for in the MRO

Returns value of the priority if it is found, 0 otherwise.

Return type Int

```
__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True
```

```
__init__ (target, name) → None
```

Method generated by attrs for class Driver.

```
__module__ = 'labgrid.driver.common'
```

```
__repr__()
```

Method generated by attrs for class Driver.

labgrid.driver.common.**check_file** (*filename, *, command_prefix=[]*)

labgrid.driver.consoleexpectmixin module

class labgrid.driver.consoleexpectmixin.**ConsoleExpectMixin**

Bases: object

Console driver mixin to implement the read, write, expect and sendline methods. It uses the internal `_read` and `_write` methods.

The class using the ConsoleExpectMixin must provide a logger and a txdelay attribute.

```
__attrs_post_init__()
```

read (*size=1, timeout=0.0*)

write (*data*)

sendline (*line*)

```

sendcontrol (char)
expect (pattern, timeout=-1)
resolve_conflicts (client)
__dict__ = mappingproxy({'__module__': 'labgrid.driver.consoleexpectmixin', '__doc__':
__module__ = 'labgrid.driver.consoleexpectmixin'
__weakref__
    list of weak references to the object (if defined)

```

labgrid.driver.deditecrelaisdriver module

```

class labgrid.driver.deditecrelaisdriver.DeditecRelaisDriver (target, name)
    Bases: labgrid.driver.common.Driver, labgrid.protocol.digitaloutputprotocol.
    DigitalOutputProtocol

    bindings = {'relais': {'DeditecRelais8', <class 'labgrid.resource.remote.NetworkDedit
    __attrs_post_init__ ()

    on_activate ()
        Called by the Target when this object has been activated

    on_deactivate ()
        Called by the Target when this object has been deactivated

    set (status)
        Implementations should set the status of the OneWirePort

    get ()
        Implementations should return the status of the OneWirePort.

    __abstractmethods__ = frozenset({})

    __attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True
    __init__ (target, name) → None
        Method generated by attrs for class DeditecRelaisDriver.

    __module__ = 'labgrid.driver.deditecrelaisdriver'

    __repr__ ()
        Method generated by attrs for class DeditecRelaisDriver.

```

labgrid.driver.dockerdriver module

Class for connecting to a docker daemon running on the host machine.

```

class labgrid.driver.dockerdriver.DockerDriver (target, name, image_uri=None,
command=None, volumes=None,
container_name=None, environ-
ment=None, host_config=None,
network_services=None)

    Bases: labgrid.protocol.powerprotocol.PowerProtocol, labgrid.driver.common.
    Driver

```

The DockerDriver is used to create docker containers. This is done via communication with a docker daemon.

When a container is created the container is labeled with an cleanup strategy identifier. Currently only one strategy is implemented. This strategy simply deletes all labgrid created containers before each test run. This is to ensure cleanup of dangling containers from crashed tests or hanging containers.

Image pruning is not done by the driver.

For detailed information about the arguments see the “Docker SDK for Python” documentation <https://docker-py.readthedocs.io/en/stable/containers.html#container-objects>

Parameters `bindings` (*dict*) – The labgrid bindings

Args passed to `docker.create_container`: `image_uri` (str): The uri of the image to fetch `command` (str): The command to execute once container has been created `volumes` (list): The volumes to declare `environment` (list): Docker environment variables to set `host_config` (dict): Docker host configuration parameters `network_services` (list): Sequence of dicts each specifying a network service that the docker container exposes.

```
bindings = {'docker_daemon': {'DockerDaemon'}}
```

```
__attrs_post_init__()
```

```
on_activate()
```

On activation: 1. Import docker module (`_client` and `_container` remain available) 2. Connect to the docker daemon 3. Pull requested image from docker registry if needed 4. Create the new container according to parameters from `conf`

```
on_deactivate()
```

Remove container after use

```
on()
```

Start the container created during activation

```
off()
```

Stop the container created during activation

```
cycle()
```

Cycle the docker container by stopping and starting it

```
__abstractmethods__ = frozenset({})
```

```
__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True,
```

```
__init__(target, name, image_uri=None, command=None, volumes=None, container_name=None,
          environment=None, host_config=None, network_services=None) → None
```

Method generated by attrs for class `DockerDriver`.

```
__module__ = 'labgrid.driver.dockerdriver'
```

```
__repr__()
```

Method generated by attrs for class `DockerDriver`.

labgrid.driver.exception module

exception `labgrid.driver.exception.ExecutionError` (*msg, stdout=None, stderr=None*)

Bases: `Exception`

```
__attrs_attrs__ = (Attribute(name='msg', default=NOTHING, validator=<instance of valid
```

```
__init__(msg, stdout=None, stderr=None) → None
```

Method generated by attrs for class `ExecutionError`.

```
__module__ = 'labgrid.driver.exception'
```


`__repr__()`
Method generated by attrs for class `ExecutionError`.

`__weakref__`
list of weak references to the object (if defined)

exception `labgrid.driver.exception.CleanUpError(msg)`

Bases: `Exception`

`__attrs_attrs__ = (Attribute(name='msg', default=NOTHING, validator=<instance of valid`

`__init__(msg) → None`
Method generated by attrs for class `CleanUpError`.

`__module__ = 'labgrid.driver.exception'`

`__repr__()`
Method generated by attrs for class `CleanUpError`.

`__weakref__`
list of weak references to the object (if defined)

labgrid.driver.externalconsoledriver module

class `labgrid.driver.externalconsoledriver.ExternalConsoleDriver(target, name, cmd, txdelay=0.0)`

Bases: `labgrid.driver.consoleexpectmixin.ConsoleExpectMixin`, `labgrid.driver.common.Driver`, `labgrid.protocol.consoleprotocol.ConsoleProtocol`

Driver implementing the `ConsoleProtocol` interface using a subprocess

`__attrs_post_init__()`

`open()`
Starts the subprocess, does nothing if it is already closed

`close()`
Stops the subprocess, does nothing if it is already closed

`on_deactivate()`
Called by the Target when this object has been deactivated

`__abstractmethods__ = frozenset({})`

`__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True`

`__init__(target, name, cmd, txdelay=0.0) → None`
Method generated by attrs for class `ExternalConsoleDriver`.

`__module__ = 'labgrid.driver.externalconsoledriver'`

`__repr__()`
Method generated by attrs for class `ExternalConsoleDriver`.

labgrid.driver.fake module

class `labgrid.driver.fake.FakeConsoleDriver(target, name, txdelay=0.0)`

Bases: `labgrid.driver.consoleexpectmixin.ConsoleExpectMixin`, `labgrid.driver.common.Driver`, `labgrid.protocol.consoleprotocol.ConsoleProtocol`

```
__attrs_post_init__()

open()

close()

__abstractmethods__ = frozenset({})

__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True

__init__(target, name, txdelay=0.0) → None
    Method generated by attrs for class FakeConsoleDriver.

__module__ = 'labgrid.driver.fake'

__repr__()
    Method generated by attrs for class FakeConsoleDriver.

class labgrid.driver.fake.FakeCommandDriver(target, name)
    Bases: labgrid.driver.commandmixin.CommandMixin, labgrid.driver.common.Driver,
    labgrid.protocol.commandprotocol.CommandProtocol

    run(*args, timeout=None)
        Run a command

    run_check(*args)
        External run_check function, only available if the driver is active. Runs the supplied command and returns
        the stdout, raises an ExecutionError otherwise.

        Parameters cmd (str) – command to run on the shell

        Returns stdout of the executed command

        Return type List[str]

    get_status()
        Get status of the Driver

    __abstractmethods__ = frozenset({})

    __attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True

    __init__(target, name) → None
        Method generated by attrs for class FakeCommandDriver.

    __module__ = 'labgrid.driver.fake'

    __repr__()
        Method generated by attrs for class FakeCommandDriver.

class labgrid.driver.fake.FakeFileTransferDriver(target, name)
    Bases: labgrid.driver.common.Driver, labgrid.protocol.filetransferprotocol.
    FileTransferProtocol

    get(*args)

    put(*args)

    __abstractmethods__ = frozenset({})

    __attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True

    __init__(target, name) → None
        Method generated by attrs for class FakeFileTransferDriver.

    __module__ = 'labgrid.driver.fake'
```

```

__repr__()
    Method generated by attrs for class FakeFileTransferDriver.

class labgrid.driver.fake.FakePowerDriver(target, name)
    Bases: labgrid.driver.common.Driver, labgrid.protocol.powerprotocol.
           PowerProtocol
    on(*args)
    off(*args)
    cycle(*args)
    __abstractmethods__ = frozenset({})
    __attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True
    __init__(target, name) → None
        Method generated by attrs for class FakePowerDriver.
    __module__ = 'labgrid.driver.fake'
    __repr__()
        Method generated by attrs for class FakePowerDriver.

```

labgrid.driver.fastbootdriver module

```

class labgrid.driver.fastbootdriver.AndroidFastbootDriver(target, name,
                                                           image=None,
                                                           sparse_size=None)
    Bases: labgrid.driver.common.Driver
    bindings = {'fastboot': {'AndroidFastboot', 'NetworkAndroidFastboot'}}
    __attrs_post_init__()
    on_activate()
        Called by the Target when this object has been activated
    on_deactivate()
        Called by the Target when this object has been deactivated
    __call__(*args)
        Call self as a function.
    boot(filename)
    flash(partition, filename)
    run(cmd)
    continue_boot()
    getvar(var)
        Return variable value via 'fastboot getvar <var>'.
    oem_getenv(var)
        Return barebox environment variable value via 'fastboot oem getenv <var>'.
    __attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True
    __init__(target, name, image=None, sparse_size=None) → None
        Method generated by attrs for class AndroidFastbootDriver.
    __module__ = 'labgrid.driver.fastbootdriver'

```

```
__repr__()
```

Method generated by attrs for class AndroidFastbootDriver.

labgrid.driver.filedigitaloutput module

```
class labgrid.driver.filedigitaloutput.FileDigitalOutputDriver(target, name,
                                                                filepath,
                                                                false_repr='0n',
                                                                true_repr='1n')
```

Bases: *labgrid.driver.common.Driver*, *labgrid.protocol.digitaloutputprotocol.DigitalOutputProtocol*

Two arbitrary string values `false_repr` and `true_repr` are defined as representations for False and True. These values are written to a file and read from it. If the file's content does not match any of the representations it defaults to False. A prime example for using this driver is Linux's sysfs.

```
bindings = {}
```

```
__attrs_post_init__()
```

```
get()
```

Implementations should return the status of the OneWirePort.

```
set(status)
```

Implementations should set the status of the OneWirePort

```
__abstractmethods__ = frozenset({})
```

```
__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True
```

```
__init__(target, name, filepath, false_repr='0n', true_repr='1n') → None
```

Method generated by attrs for class FileDigitalOutputDriver.

```
__module__ = 'labgrid.driver.filedigitaloutput'
```

```
__repr__()
```

Method generated by attrs for class FileDigitalOutputDriver.

labgrid.driver.flashromdriver module

```
class labgrid.driver.flashromdriver.FlashromDriver(target, name, image=None)
```

Bases: *labgrid.driver.common.Driver*, *labgrid.protocol.bootstrapprotocol.BootstrapProtocol*

The Flashrom driver used the flashrom utility to write an image to a raw rom. The driver is a pure wrapper of the flashrom utility

```
bindings = {'flashrom_resource': {<class 'labgrid.resource.flashrom.NetworkFlashrom'>
```

```
__attrs_post_init__()
```

```
on_activate()
```

Called by the Target when this object has been activated

```
on_deactivate()
```

Called by the Target when this object has been deactivated

```
__call__(*args)
```

Call self as a function.

```
load(filename=None)
```

```

__abstractmethods__ = frozenset({})

__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True

__init__(target, name, image=None) → None
    Method generated by attrs for class FlashromDriver.

__module__ = 'labgrid.driver.flashromdriver'

__repr__()
    Method generated by attrs for class FlashromDriver.

```

labgrid.driver.gpiodriver module

All GPIO-related drivers

```

class labgrid.driver.gpiodriver.GpioDigitalOutputDriver(target, name)
    Bases: labgrid.driver.common.Driver, labgrid.protocol.digitaloutputprotocol.
           DigitalOutputProtocol

    bindings = {'gpio': {'NetworkSysfsGPIO', 'SysfsGPIO'}}

    __attrs_post_init__()

    on_activate()
        Called by the Target when this object has been activated

    on_deactivate()
        Called by the Target when this object has been deactivated

    set(status)
        Implementations should set the status of the OneWirePort

    get()
        Implementations should return the status of the OneWirePort.

    __abstractmethods__ = frozenset({})

    __attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True

    __init__(target, name) → None
        Method generated by attrs for class GpioDigitalOutputDriver.

    __module__ = 'labgrid.driver.gpiodriver'

    __repr__()
        Method generated by attrs for class GpioDigitalOutputDriver.

```

labgrid.driver.lxaiobusdriver module

```

class labgrid.driver.lxaiobusdriver.LXAIOPBusPIODriver(target, name)
    Bases: labgrid.driver.common.Driver, labgrid.protocol.digitaloutputprotocol.
           DigitalOutputProtocol

    bindings = {'pio': {'LXAIOPBusPIO', 'NetworkLXAIOPBusPIO'}}

    __attrs_post_init__()

    on_activate()
        Called by the Target when this object has been activated

```

set (*status*)

Implementations should set the status of the OneWirePort

get ()

Implementations should return the status of the OneWirePort.

__abstractmethods__ = frozenset({})

__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True

__init__ (*target, name*) → None

Method generated by attrs for class LXAIOBusPIODriver.

__module__ = 'labgrid.driver.lxaibusdriver'

__repr__ ()

Method generated by attrs for class LXAIOBusPIODriver.

labgrid.driver.modbusdriver module

class labgrid.driver.modbusdriver.**ModbusCoilDriver** (*target, name*)

Bases: *labgrid.driver.common.Driver*, *labgrid.protocol.digitaloutputprotocol.DigitalOutputProtocol*

bindings = {'coil': 'ModbusTCPCoil'}

__attrs_post_init__ ()

on_activate ()

Called by the Target when this object has been activated

on_deactivate ()

Called by the Target when this object has been deactivated

set (*status*)

Implementations should set the status of the OneWirePort

get ()

Implementations should return the status of the OneWirePort.

__abstractmethods__ = frozenset({})

__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True

__init__ (*target, name*) → None

Method generated by attrs for class ModbusCoilDriver.

__module__ = 'labgrid.driver.modbusdriver'

__repr__ ()

Method generated by attrs for class ModbusCoilDriver.

labgrid.driver.onewiredriver module

class labgrid.driver.onewiredriver.**OneWirePIODriver** (*target, name*)

Bases: *labgrid.driver.common.Driver*, *labgrid.protocol.digitaloutputprotocol.DigitalOutputProtocol*

bindings = {'port': 'OneWirePIO'}

__attrs_post_init__ ()

```

on_activate()
    Called by the Target when this object has been activated

on_deactivate()
    Called by the Target when this object has been deactivated

set(status)
    Implementations should set the status of the OneWirePort

get()
    Implementations should return the status of the OneWirePort.

__abstractmethods__ = frozenset({})

__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True
__init__(target, name) → None
    Method generated by attrs for class OneWirePIODriver.

__module__ = 'labgrid.driver.onewiredriver'

__repr__()
    Method generated by attrs for class OneWirePIODriver.

```

labgrid.driver.openocddriver module

```

class labgrid.driver.openocddriver.OpenOCDDriver(target, name, config, search=[], im-
    age=None)
    Bases: labgrid.driver.common.Driver, labgrid.protocol.bootstrapprotocol.BootstrapProtocol

    bindings = {'interface': {'AlteraUSBBlaster', 'NetworkAlteraUSBBlaster'}}

    __attrs_post_init__()

    load(filename=None)

    execute(commands: list)

    __abstractmethods__ = frozenset({})

    __attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True
    __init__(target, name, config, search=[], image=None) → None
        Method generated by attrs for class OpenOCDDriver.

    __module__ = 'labgrid.driver.openocddriver'

    __repr__()
        Method generated by attrs for class OpenOCDDriver.

```

labgrid.driver.powerdriver module

```

class labgrid.driver.powerdriver.PowerResetMixin
    Bases: labgrid.protocol.resetprotocol.ResetProtocol

    ResetMixin implements the ResetProtocol for drivers which support the PowerProtocol

    priorities = {<class 'labgrid.protocol.resetprotocol.ResetProtocol'>: -10}

    __attrs_post_init__()

    reset()

```

```
__abstractmethods__ = frozenset({})

__attrs_attrs__ = ()

__init__() → None
    Method generated by attrs for class PowerResetMixin.

__module__ = 'labgrid.driver.powerdriver'

__repr__()
    Method generated by attrs for class PowerResetMixin.

class labgrid.driver.powerdriver.ManualPowerDriver(target, name)
    Bases: labgrid.driver.common.Driver, labgrid.driver.powerdriver.
    PowerResetMixin, labgrid.protocol.powerprotocol.PowerProtocol

    ManualPowerDriver - Driver to tell the user to control a target's power

    on()

    off()

    cycle()

    __abstractmethods__ = frozenset({})

    __attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True
    __init__(target, name) → None
        Method generated by attrs for class ManualPowerDriver.

    __module__ = 'labgrid.driver.powerdriver'

    __repr__()
        Method generated by attrs for class ManualPowerDriver.

class labgrid.driver.powerdriver.SiSPMPowerDriver(target, name, delay=2.0)
    Bases: labgrid.driver.common.Driver, labgrid.driver.powerdriver.
    PowerResetMixin, labgrid.protocol.powerprotocol.PowerProtocol

    SiSPMPowerDriver - Driver using a SiS-PM (Silver Shield PM) to control a target's power using the sispmtcl
    tool - http://sispmctl.sourceforge.net/

    bindings = {'port': {'NetworkSiSPMPowerPort', 'SiSPMPowerPort'}}

    __attrs_post_init__()

    on()

    off()

    cycle()

    get()

    __abstractmethods__ = frozenset({})

    __attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True
    __init__(target, name, delay=2.0) → None
        Method generated by attrs for class SiSPMPowerDriver.

    __module__ = 'labgrid.driver.powerdriver'

    __repr__()
        Method generated by attrs for class SiSPMPowerDriver.
```



```

class labgrid.driver.powerdriver.ExternalPowerDriver(target, name, cmd_on, cmd_off,
                                                    cmd_cycle=None, delay=2.0)
    Bases: labgrid.driver.common.Driver, labgrid.driver.powerdriver.
           PowerResetMixin, labgrid.protocol.powerprotocol.PowerProtocol
    ExternalPowerDriver - Driver using an external command to control a target's power
    on()
    off()
    cycle()
    __abstractmethods__ = frozenset({})
    __attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True
    __init__(target, name, cmd_on, cmd_off, cmd_cycle=None, delay=2.0) → None
        Method generated by attrs for class ExternalPowerDriver.
    __module__ = 'labgrid.driver.powerdriver'
    __repr__()
        Method generated by attrs for class ExternalPowerDriver.

class labgrid.driver.powerdriver.NetworkPowerDriver(target, name, delay=2.0)
    Bases: labgrid.driver.common.Driver, labgrid.driver.powerdriver.
           PowerResetMixin, labgrid.protocol.powerprotocol.PowerProtocol
    NetworkPowerDriver - Driver using a networked power switch to control a target's power
    bindings = {'port': <class 'labgrid.resource.power.NetworkPowerPort'>}
    __attrs_post_init__()
    on_activate()
        Called by the Target when this object has been activated
    on()
    off()
    cycle()
    get()
    __abstractmethods__ = frozenset({})
    __attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True
    __init__(target, name, delay=2.0) → None
        Method generated by attrs for class NetworkPowerDriver.
    __module__ = 'labgrid.driver.powerdriver'
    __repr__()
        Method generated by attrs for class NetworkPowerDriver.

class labgrid.driver.powerdriver.DigitalOutputPowerDriver(target, name, de-
                                                         lay=1.0)
    Bases: labgrid.driver.common.Driver, labgrid.driver.powerdriver.
           PowerResetMixin, labgrid.protocol.powerprotocol.PowerProtocol
    DigitalOutputPowerDriver uses a DigitalOutput to control the power of a DUT.
    bindings = {'output': <class 'labgrid.protocol.digitaloutputprotocol.DigitalOutputPro
    __attrs_post_init__()

```

```
on()
off()
cycle()
get()

__abstractmethods__ = frozenset({})

__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True
__init__(target, name, delay=1.0) → None
    Method generated by attrs for class DigitalOutputPowerDriver.

__module__ = 'labgrid.driver.powerdriver'

__repr__()
    Method generated by attrs for class DigitalOutputPowerDriver.

class labgrid.driver.powerdriver.YKUSHPowerDriver(target, name, delay=2.0)
    Bases: labgrid.driver.common.Driver, labgrid.driver.powerdriver.
    PowerResetMixin, labgrid.protocol.powerprotocol.PowerProtocol

    YKUSHPowerDriver - Driver using a YEPKIT YKUSH switchable USB hub to control a target's power -
    https://www.yepkit.com/products/ykush

    bindings = {'port': 'YKUSHPowerPort'}

    __attrs_post_init__()

    on()
    off()
    cycle()
    get()

    __abstractmethods__ = frozenset({})

    __attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True
    __init__(target, name, delay=2.0) → None
        Method generated by attrs for class YKUSHPowerDriver.

    __module__ = 'labgrid.driver.powerdriver'

    __repr__()
        Method generated by attrs for class YKUSHPowerDriver.

class labgrid.driver.powerdriver.USBPowerDriver(target, name, delay=2.0)
    Bases: labgrid.driver.common.Driver, labgrid.driver.powerdriver.
    PowerResetMixin, labgrid.protocol.powerprotocol.PowerProtocol

    USBPowerDriver - Driver using a power switchable USB hub and the uhubctl tool (https://github.com/mvp/uhubctl) to control a target's power

    bindings = {'hub': {'NetworkUSBPowerPort', 'USBPowerPort'}}

    __attrs_post_init__()

    on()
    off()
    cycle()
```

```

get ()

__abstractmethods__ = frozenset({})

__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True

__init__ (target, name, delay=2.0) → None
    Method generated by attrs for class USBPowerDriver.

__module__ = 'labgrid.driver.powerdriver'

__repr__ ()
    Method generated by attrs for class USBPowerDriver.

class labgrid.driver.powerdriver.PDUDaemonDriver (target, name, delay=5)
    Bases: labgrid.driver.common.Driver, labgrid.driver.powerdriver.
    PowerResetMixin, labgrid.protocol.powerprotocol.PowerProtocol

    PDUDaemonDriver - Driver using a PDU port available via pdudaemon

    bindings = {'port': 'PDUDaemonPort'}

    __attrs_post_init__ ()

    on_activate ()
        Called by the Target when this object has been activated

    on ()

    off ()

    cycle ()

    get ()

    __abstractmethods__ = frozenset({})

    __attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True

    __init__ (target, name, delay=5) → None
        Method generated by attrs for class PDUDaemonDriver.

    __module__ = 'labgrid.driver.powerdriver'

    __repr__ ()
        Method generated by attrs for class PDUDaemonDriver.

```

labgrid.driver.pyvisadriver module

```

class labgrid.driver.pyvisadriver.PyVISADriver (target, name)
    Bases: labgrid.driver.common.Driver

    The PyVISADriver provides a transparent layer to the PyVISA module allowing to get a pyvisa resource

    Parameters bindings (dict) – driver to use with PyVISA

    bindings = {'pyvisa_resource': 'PyVISADevice'}

    __attrs_post_init__ ()

    on_activate ()
        Called by the Target when this object has been activated

    on_deactivate ()
        Called by the Target when this object has been deactivated

```

```
get_session()

__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True
__init__(target, name) → None
    Method generated by attrs for class PyVISADriver.

__module__ = 'labgrid.driver.pyvisadriver'

__repr__()
    Method generated by attrs for class PyVISADriver.
```

labgrid.driver.qemudriver module

The QEMUDriver implements a driver to use a QEMU target

```
class labgrid.driver.qemudriver.QEMUDriver(target, name, qemu_bin, machine, cpu,
                                           memory, extra_args, boot_args=None,
                                           kernel=None, disk=None, rootfs=None,
                                           dtb=None, flash=None)

Bases: labgrid.driver.consoleexpectmixin.ConsoleExpectMixin, labgrid.driver.
common.Driver, labgrid.protocol.powerprotocol.PowerProtocol, labgrid.
protocol.consoleprotocol.ConsoleProtocol
```

The QEMUDriver implements an interface to start targets as qemu instances.

The kernel, flash, rootfs and dtb arguments refer to images and paths declared in the environment configuration.

Parameters

- **qemu_bin** (*str*) – reference to the tools key for the QEMU binary
- **machine** (*str*) – QEMU machine type
- **cpu** (*str*) – QEMU cpu type
- **memory** (*str*) – QEMU memory size (ends with M or G)
- **extra_args** (*str*) – extra QEMU arguments, they are passed directly to the QEMU binary
- **boot_args** (*str*) – optional, additional kernel boot argument
- **kernel** (*str*) – optional, reference to the images key for the kernel
- **disk** (*str*) – optional, reference to the images key for the disk image
- **flash** (*str*) – optional, reference to the images key for the flash image
- **rootfs** (*str*) – optional, reference to the paths key for use as the virtio-9p filesystem
- **dtb** (*str*) – optional, reference to the image key for the device tree

```
__attrs_post_init__()
```

```
on_activate()
```

Called by the Target when this object has been activated

```
on_deactivate()
```

Called by the Target when this object has been deactivated

```
on()
```

Start the QEMU subprocess, accept the unix socket connection and afterwards start the emulator using a QMP Command

```

off()
    Stop the emulator using a monitor command and await the exitcode

cycle()
    Cycle the emulator by restarting it

monitor_command(command)
    Execute a monitor_command via the QMP

__abstractmethods__ = frozenset({})

__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True

__init__(target, name, qemu_bin, machine, cpu, memory, extra_args, boot_args=None, kernel=None,
    disk=None, rootfs=None, dtb=None, flash=None) → None
    Method generated by attrs for class QEMUDriver.

__module__ = 'labgrid.driver.qemudriver'

__repr__()
    Method generated by attrs for class QEMUDriver.

```

labgrid.driver.quartushpsdriver module

```

class labgrid.driver.quartushpsdriver.QuartusHPSDriver(target, name, image=None)
    Bases: labgrid.driver.common.Driver

    bindings = {'interface': {'AlteraUSBBlaster', 'NetworkAlteraUSBBlaster'}}

    __attrs_post_init__()

    flash(filename=None, address=0)

    erase(address=None, size=None)

    __attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True

    __init__(target, name, image=None) → None
        Method generated by attrs for class QuartusHPSDriver.

    __module__ = 'labgrid.driver.quartushpsdriver'

    __repr__()
        Method generated by attrs for class QuartusHPSDriver.

```

labgrid.driver.resetdriver module

```

class labgrid.driver.resetdriver.DigitalOutputResetDriver(target, name, de-
    lay=1.0)
    Bases: labgrid.driver.common.Driver, labgrid.protocol.resetprotocol.
    ResetProtocol

    DigitalOutputResetDriver - Driver using a DigitalOutput to reset the target

    bindings = {'output': <class 'labgrid.protocol.digitaloutputprotocol.DigitalOutputPro

    __attrs_post_init__()

    reset()

    __abstractmethods__ = frozenset({})

    __attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True

```

```
__init__(target, name, delay=1.0) → None
    Method generated by attrs for class DigitalOutputResetDriver.

__module__ = 'labgrid.driver.resetdriver'

__repr__()
```

Method generated by attrs for class DigitalOutputResetDriver.

labgrid.driver.serialdigitaloutput module

```
class labgrid.driver.serialdigitaloutput.SerialPortDigitalOutputDriver(target,
                                                                    name,
                                                                    sig-
                                                                    nal,
                                                                    in-
                                                                    vert)

Bases: labgrid.driver.common.Driver, labgrid.protocol.digitaloutputprotocol.
        DigitalOutputProtocol
```

Controls the state of a GPIO using the control lines of a serial port.

This driver uses the flow-control pins of a serial port (for example an USB-UART-dongle) to control some external power switch. You may connect some kind of relay board to the flow control pins.

The serial port should NOT be used for serial communication at the same time. This will probably reset the flow-control signals.

Usable signals are DTR and RTS.

```
bindings = {'serial': <class 'labgrid.driver.serialdriver.SerialDriver'>}
```

```
__attrs_post_init__()
```

```
get()
```

Implementations should return the status of the OneWirePort.

```
set(value)
```

Implementations should set the status of the OneWirePort

```
__abstractmethods__ = frozenset({})
```

```
__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True
```

```
__init__(target, name, signal, invert) → None
    Method generated by attrs for class SerialPortDigitalOutputDriver.
```

```
__module__ = 'labgrid.driver.serialdigitaloutput'
```

```
__repr__()
```

Method generated by attrs for class SerialPortDigitalOutputDriver.

labgrid.driver.serialdriver module

```
class labgrid.driver.serialdriver.SerialDriver(target, name, txdelay=0.0, timeout=3.0)

Bases: labgrid.driver.consoleexpectmixin.ConsoleExpectMixin, labgrid.driver.
        common.Driver, labgrid.protocol.consoleprotocol.ConsoleProtocol
```

Driver implementing the ConsoleProtocol interface over a SerialPort connection

```
bindings = {'port': {'NetworkSerialPort', 'SerialPort'}}
```

```

message = 'The installed pyserial version does not contain important RFC2217 fixes.\nY
__attrs_post_init__()
on_activate()
    Called by the Target when this object has been activated
on_deactivate()
    Called by the Target when this object has been deactivated
open()
    Opens the serialport, does nothing if it is already closed
__abstractmethods__ = frozenset({})
__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True
__init__(target, name, txdelay=0.0, timeout=3.0) → None
    Method generated by attrs for class SerialDriver.
__module__ = 'labgrid.driver.serialdriver'
__repr__()
    Method generated by attrs for class SerialDriver.
close()
    Closes the serialport, does nothing if it is already closed

```

labgrid.driver.shelldriver module

The ShellDriver provides the CommandProtocol, ConsoleProtocol and InfoProtocol on top of a SerialPort.

```

class labgrid.driver.shelldriver.ShellDriver(target, name, prompt, login_prompt,
                                             username, password="", keyfile="",
                                             login_timeout=60, console_ready="",
                                             await_login_timeout=2)

```

Bases: *labgrid.driver.commandmixin.CommandMixin, labgrid.driver.common.Driver, labgrid.protocol.commandprotocol.CommandProtocol, labgrid.protocol.filetransferprotocol.FileTransferProtocol*

ShellDriver - Driver to execute commands on the shell ShellDriver binds on top of a ConsoleProtocol.

Parameters

- **prompt** (*regex*) – the shell prompt to detect
- **login_prompt** (*regex*) – the login prompt to detect
- **username** (*str*) – username to login with
- **password** (*str*) – password to login with
- **keyfile** (*str*) – keyfile to bind mount over users authorized keys
- **login_timeout** (*int*) – optional, timeout for login prompt detection

```

bindings = {'console': <class 'labgrid.protocol.consoleprotocol.ConsoleProtocol'>}

```

```

__attrs_post_init__()
on_activate()
    Called by the Target when this object has been activated
on_deactivate()
    Called by the Target when this object has been deactivated

```

run (*cmd*, *timeout=30.0*, *codec='utf-8'*, *decodeerrors='strict'*)

Run a command

get_status ()

Returns the status of the shell-driver. 0 means not connected/found, 1 means shell

put_ssh_key (*keyfile_path*)

put_bytes (*buf: bytes*, *remotefile: str*)

Upload a file to the target. Will silently overwrite the remote file if it already exists.

Parameters

- **buf** (*bytes*) – file contents
- **remotefile** (*str*) – destination filename on the target

Raises *ExecutionError* – if something went wrong

put (*localfile: str*, *remotefile: str*)

Upload a file to the target. Will silently overwrite the remote file if it already exists.

Parameters

- **localfile** (*str*) – source filename on the local machine
- **remotefile** (*str*) – destination filename on the target

Raises

- *IOError* – if the provided localfile could not be found
- *ExecutionError* – if something else went wrong

get_bytes (*remotefile: str*)

Download a file from the target.

Parameters **remotefile** (*str*) – source filename on the target

Returns (*bytes*) file contents

Raises *ExecutionError* – if something went wrong

get (*remotefile: str*, *localfile: str*)

Download a file from the target. Will silently overwrite the local file if it already exists.

Parameters

- **remotefile** (*str*) – source filename on the target
- **localfile** (*str*) – destination filename on the local machine (can be relative)

Raises

- *IOError* – if localfile could not be written
- *ExecutionError* – if something went wrong

run_script (*data: bytes*, *timeout: int = 60*)

Upload a script to the target and run it.

Parameters

- **data** (*bytes*) – script data
- **timeout** (*int*) – timeout for the script to finish execution

Returns *str*, *stderr: str*, *return_value: int*)

Return type Tuple of (stdout

Raises `ExecutionError` – if something went wrong

run_script_file (*scriptfile*: str, *args, timeout: int = 60)

Upload a script file to the target and run it.

Parameters

- **scriptfile** (str) – source file on the local file system to upload to the target
- ***args** – (list of str): any arguments for the script as positional arguments
- **timeout** (int) – timeout for the script to finish execution

Returns str, stderr: str, return_value: int)

Return type Tuple of (stdout

Raises

- `ExecutionError` – if something went wrong
- `IOError` – if the provided localfile could not be found

```
__abstractmethods__ = frozenset({})
```

```
__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True
```

```
__init__ (target, name, prompt, login_prompt, username, password=", keyfile=", login_timeout=60,
          console_ready=", await_login_timeout=2) → None
Method generated by attrs for class ShellDriver.
```

```
__module__ = 'labgrid.driver.shelldriver'
```

```
__repr__ ()
Method generated by attrs for class ShellDriver.
```

labgrid.driver.sigrokdriver module

```
class labgrid.driver.sigrokdriver.SigrokCommon (target, name)
```

Bases: `labgrid.driver.common.Driver`

```
__attrs_post_init__ ()
```

```
on_activate ()
Called by the Target when this object has been activated
```

```
on_deactivate ()
Called by the Target when this object has been deactivated
```

```
__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True
```

```
__init__ (target, name) → None
Method generated by attrs for class SigrokCommon.
```

```
__module__ = 'labgrid.driver.sigrokdriver'
```

```
__repr__ ()
Method generated by attrs for class SigrokCommon.
```

```
class labgrid.driver.sigrokdriver.SigrokDriver (target, name)
```

Bases: `labgrid.driver.sigrokdriver.SigrokCommon`

The SigrokDriver uses sigrok-cli to record samples and expose them as python dictionaries.

Parameters **bindings** (*dict*) – driver to use with sigrok

```
bindings = {'sigrok': {<class 'labgrid.resource.sigrok.SigrokDevice'>, <class 'labgrid.resource.sigrok.SigrokPowerDriver'>}}
```

capture (*filename*, *samplerate*='200k')

stop ()

analyze (*args*, *filename*=None)

__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True))

__init__ (*target*, *name*) → None

Method generated by attrs for class SigrokDriver.

__module__ = 'labgrid.driver.sigrokdriver'

__repr__ ()

Method generated by attrs for class SigrokDriver.

```
class labgrid.driver.sigrokdriver.SigrokPowerDriver(target, name, delay=3.0,
                                                    max_voltage=None,
                                                    max_current=None)
```

Bases: *labgrid.driver.sigrokdriver.SigrokCommon*, *labgrid.driver.powerdriver.PowerResetMixin*, *labgrid.protocol.powerprotocol.PowerProtocol*

The SigrokPowerDriverDriver uses sigrok-cli to control a PSU and collect measurements.

Parameters **bindings** (*dict*) – driver to use with sigrok

```
bindings = {'sigrok': {<class 'labgrid.resource.udev.SigrokUSBSerialDevice'>, <class 'labgrid.resource.udev.SigrokPowerDriver'>}}
```

on ()

off ()

cycle ()

set_voltage_target (*value*)

set_current_limit (*value*)

get ()

measure ()

__abstractmethods__ = frozenset({})

__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True))

__init__ (*target*, *name*, *delay*=3.0, *max_voltage*=None, *max_current*=None) → None

Method generated by attrs for class SigrokPowerDriver.

__module__ = 'labgrid.driver.sigrokdriver'

__repr__ ()

Method generated by attrs for class SigrokPowerDriver.

labgrid.driver.smallubootdriver module

```
class labgrid.driver.smallubootdriver.SmallUBootDriver(target, name, prompt=",
    autoboot='stop autoboot',
    password=", interrupt='\n',
    init_commands=NOTHING,
    password_prompt='enter Password:',
    boot_expression='U-
    Boot 20\nd+', boot-
    string='Linux version \nd', boot_command='run bootcmd', boot_secret='a',
    login_timeout=60)
```

Bases: `labgrid.driver.ubootdriver.UBootDriver`

SmallUBootDriver is meant as a driver for UBoot with only little functionality compared to standard a standard UBoot. Especially is copes with the following limitations:

- The UBoot does not have a real password-prompt but can be activated by entering a “secret” after a message was displayed.
- The command line is does not have a build-in echo command. Thus this driver uses ‘Unknown Command’ messages as marker before and after the output of a command.
- Since there is no echo we can not return the exit code of the command. Commands will always return 0 unless the command was not found.

This driver needs the following features activated in UBoot to work:

- The UBoot must not have real password prompt. Instead it must be keyword activated. For example it should be activated by a dialog like the following: UBoot: “Autobooting in 1s...” Labgrid: “secret” UBoot: <switching to console>
- The UBoot must be able to parse multiple commands in a single line separated by “;”.
- The UBoot must support the “bootm” command to boot from a memory location.

This driver was created especially for the following devices:

- TP-Link WR841 v11

Parameters

- **boot_secret** (*str*) – optional, secret used to unlock prompt
- **login_timeout** (*int*) – optional, timeout for login prompt detection,

boot (*name*)

Boot the device from the given memory location using ‘bootm’.

Parameters **name** (*str*) – address to boot

__abstractmethods__ = **frozenset**({})

__attrs_attrs__ = (**Attribute**(name='target', default=NOTHING, validator=None, repr=True

__init__(target, name, prompt=", autoboot='stop autoboot', password=", interrupt='\n', init_commands=NOTHING, password_prompt='enter Password:', boot_expression='U-Boot 20\nd+', bootstring='Linux version \nd', boot_command='run bootcmd', boot_secret='a', login_timeout=60) → None

Method generated by attrs for class SmallUBootDriver.

```
__module__ = 'labgrid.driver.smallubootdriver'

__repr__ ()
    Method generated by attrs for class SmallUBootDriver.
```

labgrid.driver.sshdriver module

The SSHDriver uses SSH as a transport to implement CommandProtocol and FileTransferProtocol

```
class labgrid.driver.sshdriver.SSHDriver (target, name, keyfile="", stderr_merge=False)
    Bases:      labgrid.driver.commandmixin.CommandMixin,      labgrid.driver.common.
    Driver, labgrid.protocol.commandprotocol.CommandProtocol, labgrid.protocol.
    filetransferprotocol.FileTransferProtocol

    SSHDriver - Driver to execute commands via SSH

    bindings = {'networkservice':  'NetworkService'}

    priorities = {<class 'labgrid.protocol.commandprotocol.CommandProtocol'>:  10, <class
    __attrs_post_init__ ()

    on_activate ()
        Called by the Target when this object has been activated

    on_deactivate ()
        Called by the Target when this object has been deactivated

    run (cmd, codec='utf-8', decodeerrors='strict', timeout=None)
        Run a command

    interact (cmd=None)

    scp (*, src, dst)

    rsync (*, src, dst, extra=[])

    sshfs (*, path, mountpoint)

    get_status ()
        The SSHDriver is always connected, return 1

    put (filename, remotepath="")

    get (filename, destination='.')

    __abstractmethods__ = frozenset({})

    __attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True)

    __init__ (target, name, keyfile="", stderr_merge=False) → None
        Method generated by attrs for class SSHDriver.

    __module__ = 'labgrid.driver.sshdriver'

    __repr__ ()
        Method generated by attrs for class SSHDriver.
```

labgrid.driver.ubootdriver module

The U-Boot Module contains the UBootDriver

```
class labgrid.driver.ubootdriver.UBootDriver(target, name, prompt="", autoboot='stop
autoboot', password="", interrupt='n',
init_commands=NOTHING, password_prompt='enter Password:',
boot_expression='U-Boot 20\d+',
bootstring='Linux version \d',
boot_command='run bootcmd', login_timeout=30)
```

Bases: `labgrid.driver.commandmixin.CommandMixin`, `labgrid.driver.common.Driver`, `labgrid.protocol.commandprotocol.CommandProtocol`, `labgrid.protocol.linuxbootprotocol.LinuxBootProtocol`

UBootDriver - Driver to control uboot via the console. UBootDriver binds on top of a ConsoleProtocol.

Parameters

- **prompt** (*str*) – The default UBoot Prompt
- **password** (*str*) – optional password to unlock UBoot
- **init_commands** (*Tuple[str]*) – a tuple of commands to run after unlock
- **interrupt** (*str*) – interrupt character to use to go to prompt
- **password_prompt** (*str*) – string to detect the password prompt
- **boot_expression** (*str*) – string to search for on UBoot start
- **bootstring** (*str*) – string that indicates that the Kernel is booting
- **boot_command** (*str*) – optional boot command to boot target
- **login_timeout** (*int*) – optional, timeout for login prompt detection

```
bindings = {'console': <class 'labgrid.protocol.consoleprotocol.ConsoleProtocol'>}
```

```
__attrs_post_init__()
```

```
on_activate()
```

Activate the UBootDriver

This function checks for a prompt and awaits it if not already active

```
on_deactivate()
```

Deactivate the UBootDriver

Simply sets the internal status to 0

```
run(cmd, timeout=30)
```

Runs the specified command on the shell and returns the output.

Parameters

- **cmd** (*str*) – command to run on the shell
- **timeout** (*int*) – optional, how long to wait for completion

Returns if successful, None otherwise

Return type `Tuple[List[str], List[str], int]`

```
get_status()
```

Retrieve status of the UBootDriver. 0 means inactive, 1 means active.

Returns status of the driver

Return type `int`

reset ()

Reset the board via a CPU reset

await_boot ()

Wait for the initial Linux version string to verify we successfully jumped into the kernel.

boot (name)

Boot the default or a specific boot entry

Parameters **name** (*str*) – name of the entry to boot

__abstractmethods__ = frozenset({})

__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True

__init__ (target, name, prompt=", autoboot='stop autoboot', password=", interrupt='\n',
init_commands=NOTHING, password_prompt='enter Password:', boot_expression='U-
Boot 20\d+', bootstring='Linux version \d', boot_command='run bootcmd', lo-
gin_timeout=30) → None

Method generated by attrs for class UBootDriver.

__module__ = 'labgrid.driver.ubootdriver'

__repr__ ()

Method generated by attrs for class UBootDriver.

labgrid.driver.usbloader module

class labgrid.driver.usbloader.**MXSUSBDriver** (target, name, image=None)

Bases: [labgrid.driver.common.Driver](#), [labgrid.protocol.bootstrapprotocol.BootstrapProtocol](#)

bindings = {'loader': {'MXSUSBLoader', 'NetworkMXSUSBLoader'}}

__attrs_post_init__ ()

on_activate ()

Called by the Target when this object has been activated

on_deactivate ()

Called by the Target when this object has been deactivated

load (filename=None)

__abstractmethods__ = frozenset({})

__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True

__init__ (target, name, image=None) → None

Method generated by attrs for class MXSUSBDriver.

__module__ = 'labgrid.driver.usbloader'

__repr__ ()

Method generated by attrs for class MXSUSBDriver.

class labgrid.driver.usbloader.**IMXUSBDriver** (target, name, image=None)

Bases: [labgrid.driver.common.Driver](#), [labgrid.protocol.bootstrapprotocol.BootstrapProtocol](#)

bindings = {'loader': {'IMXUSBLoader', 'MXSUSBLoader', 'NetworkIMXUSBLoader', 'Networ

__attrs_post_init__ ()

```

    on_activate()
        Called by the Target when this object has been activated

    on_deactivate()
        Called by the Target when this object has been deactivated

    load(filename=None)

    __abstractmethods__ = frozenset({})

    __attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True

    __init__(target, name, image=None) → None
        Method generated by attrs for class IMXUSBDriver.

    __module__ = 'labgrid.driver.usbloader'

    __repr__()
        Method generated by attrs for class IMXUSBDriver.

class labgrid.driver.usbloader.RKUSBDriver(target, name, image=None,
                                           usb_loader=None)
    Bases: labgrid.driver.common.Driver, labgrid.protocol.bootstrapprotocol.
           BootstrapProtocol

    bindings = {'loader': {'NetworkRKUSBLoader', 'RKUSBLoader'}}

    __attrs_post_init__()

    on_activate()
        Called by the Target when this object has been activated

    on_deactivate()
        Called by the Target when this object has been deactivated

    load(filename=None)

    __abstractmethods__ = frozenset({})

    __attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True

    __init__(target, name, image=None, usb_loader=None) → None
        Method generated by attrs for class RKUSBDriver.

    __module__ = 'labgrid.driver.usbloader'

    __repr__()
        Method generated by attrs for class RKUSBDriver.

class labgrid.driver.usbloader.UUUDriver(target, name, image=None, cmd='spl')
    Bases: labgrid.driver.common.Driver, labgrid.protocol.bootstrapprotocol.
           BootstrapProtocol

    bindings = {'loader': {'IMXUSBLoader', 'MXSUSBLoader', 'NetworkIMXUSBLoader', 'Networ

    __attrs_post_init__()

    on_activate()
        Called by the Target when this object has been activated

    on_deactivate()
        Called by the Target when this object has been deactivated

    load(filename=None)

    __abstractmethods__ = frozenset({})

```

```
__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True)
__init__(target, name, image=None, cmd='spl') → None
    Method generated by attrs for class UUUDriver.
__module__ = 'labgrid.driver.usbloader'
__repr__()
    Method generated by attrs for class UUUDriver.
```

labgrid.driver.usbsdmuxdriver module

```
class labgrid.driver.usbsdmuxdriver.USBSDMuxDriver(target, name)
    Bases: labgrid.driver.common.Driver

    The USBSDMuxDriver uses the usbsdmux tool (https://github.com/pengutronix/usbsdmux) to control the USB-SD-Mux hardware

    Parameters bindings (dict) – driver to use with usbsdmux

    bindings = {'mux': {'NetworkUSBSDMuxDevice', 'USBSDMuxDevice'}}
    __attrs_post_init__()
    set_mode(mode)
    __attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True)
    __init__(target, name) → None
        Method generated by attrs for class USBSDMuxDriver.
    __module__ = 'labgrid.driver.usbsdmuxdriver'
    __repr__()
        Method generated by attrs for class USBSDMuxDriver.
```

labgrid.driver.usbsdwiredriver module

```
class labgrid.driver.usbsdwiredriver.USBSDWireDriver(target, name)
    Bases: labgrid.driver.common.Driver

    The USBSDWireDriver uses the sd-mux-ctrl tool to control SDWire hardware

    Parameters bindings (dict) – driver to use with usbsdmux

    bindings = {'mux': {'NetworkUSBSDWireDevice', 'USBSDWireDevice'}}
    __attrs_post_init__()
    set_mode(mode)
    __attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True)
    __init__(target, name) → None
        Method generated by attrs for class USBSDWireDriver.
    __module__ = 'labgrid.driver.usbsdwiredriver'
    __repr__()
        Method generated by attrs for class USBSDWireDriver.
```


labgrid.driver.usbstoragedriver module

```
class labgrid.driver.usbstoragedriver.Mode
```

Bases: `enum.Enum`

An enumeration.

DD = 'dd'

BMAPTOOL = 'bmaptool'

__module__ = 'labgrid.driver.usbstoragedriver'

```
class labgrid.driver.usbstoragedriver.USBStorageDriver(target, name, image=None)
```

Bases: `labgrid.driver.common.Driver`

bindings = {'storage': {'NetworkUSBMassStorage', 'NetworkUSBSDMuxDevice', 'NetworkUSB

__attrs_post_init__()

on_activate()

Called by the Target when this object has been activated

on_deactivate()

Called by the Target when this object has been deactivated

write_image(filename=None, mode=<Mode.DD: 'dd'>, partition=None, skip=0, seek=0)

Writes the file specified by filename or if not specified by config image subkey to the bound USB storage root device or partition.

Parameters

- **filename** (*str*) – optional, path to the image to write to bound USB storage
- **mode** (*Mode*) – optional, Mode.DD or Mode.BMAPTOOL (defaults to Mode.DD)
- **partition** (*int or None*) – optional, write to the specified partition or None for writing to root device (defaults to None)
- **skip** (*int*) – optional, skip n 512-sized blocks at start of input file (defaults to 0)
- **seek** (*int*) – optional, skip n 512-sized blocks at start of output (defaults to 0)

get_size()

__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True

__init__(target, name, image=None) → None

Method generated by attrs for class USBStorageDriver.

__module__ = 'labgrid.driver.usbstoragedriver'

__repr__()

Method generated by attrs for class USBStorageDriver.

```
class labgrid.driver.usbstoragedriver.NetworkUSBStorageDriver(target, name, im-
```

age=None)

Bases: `labgrid.driver.usbstoragedriver.USBStorageDriver`

__attrs_post_init__()

__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True

__init__(target, name, image=None) → None

Method generated by attrs for class NetworkUSBStorageDriver.

__module__ = 'labgrid.driver.usbstoragedriver'

```
__repr__()
```

Method generated by attrs for class NetworkUSBStorageDriver.

labgrid.driver.usbtmcdriver module

```
class labgrid.driver.usbtmcdriver.USBTMCDriver(target, name)
    Bases: labgrid.driver.common.Driver

    bindings = {'tmc': {'NetworkUSBTMC', 'USBTMC'}}

    __attrs_post_init__()

    on_activate()
        Called by the Target when this object has been activated

    on_deactivate()
        Called by the Target when this object has been deactivated

    command(cmd)

    query(cmd, binary=False, raw=False)

    identify()

    get_channel_info(channel)

    get_channel_values(channel)

    get_screenshot()

    get_bool(cmd)

    get_int(cmd)

    get_decimal(cmd)

    get_str(cmd)

    __attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True),)

    __init__(target, name) → None
        Method generated by attrs for class USBTMCDriver.

    __module__ = 'labgrid.driver.usbtmcdriver'

    __repr__()
        Method generated by attrs for class USBTMCDriver.
```

labgrid.driver.usbvideodriver module

```
class labgrid.driver.usbvideodriver.USBVideoDriver(target, name)
    Bases: labgrid.driver.common.Driver

    bindings = {'video': {'NetworkUSBVideo', 'USBVideo'}}

    get_caps()

    select_caps(hint=None)

    get_pipeline()

    stream(caps_hint=None)

    __attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True),)
```

```

__init__(target, name) → None
    Method generated by attrs for class USBVideoDriver.

__module__ = 'labgrid.driver.usbvideodriver'

__repr__()
    Method generated by attrs for class USBVideoDriver.

```

labgrid.driver.xenadriver module

```

class labgrid.driver.xenadriver.XenaDriver(target, name)
    Bases: labgrid.driver.common.Driver
    Xena Driver

    bindings = {'xena_manager': 'XenaManager'}

    __attrs_post_init__()

    on_activate()
        Called by the Target when this object has been activated

    on_deactivate()
        Called by the Target when this object has been deactivated

    get_session()

    __attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True,
    __init__(target, name) → None
        Method generated by attrs for class XenaDriver.

    __module__ = 'labgrid.driver.xenadriver'

    __repr__()
        Method generated by attrs for class XenaDriver.

```

labgrid.protocol package

Submodules

labgrid.protocol.bootstrapprotocol module

```

class labgrid.protocol.bootstrapprotocol.BootstrapProtocol
    Bases: abc.ABC

    abstract load(filename: str)

    __abstractmethods__ = frozenset({'load'})

    __dict__ = mappingproxy({'__module__': 'labgrid.protocol.bootstrapprotocol', 'load':
    __module__ = 'labgrid.protocol.bootstrapprotocol'

    __weakref__
        list of weak references to the object (if defined)

```

labgrid.protocol.commandprotocol module

```
class labgrid.protocol.commandprotocol.CommandProtocol
```

Bases: abc.ABC

Abstract class for the CommandProtocol

```
abstract run (command: str)
```

Run a command

```
abstract run_check (command: str)
```

Run a command, return str if succesful, ExecutionError otherwise

```
abstract get_status ()
```

Get status of the Driver

```
abstract wait_for ()
```

Wait for a shell command to return with the specified output

```
abstract poll_until_success ()
```

Repeatedly call a shell command until it succeeds

```
__abstractmethods__ = frozenset({'get_status', 'poll_until_success', 'run', 'run_check
```

```
__dict__ = mappingproxy({'__module__': 'labgrid.protocol.commandprotocol', '__doc__':
```

```
__module__ = 'labgrid.protocol.commandprotocol'
```

```
__weakref__
```

list of weak references to the object (if defined)

labgrid.protocol.consoleprotocol module

```
class labgrid.protocol.consoleprotocol.ConsoleProtocol
```

Bases: abc.ABC

Abstract class for the ConsoleProtocol

```
abstract read ()
```

Read data from underlying port

```
abstract write (data: bytes)
```

Write data to underlying port

```
sendline (line: str)
```

```
sendcontrol (char: str)
```

```
expect (pattern: str)
```

```
class Client
```

Bases: abc.ABC

```
abstract get_console_matches ()
```

```
abstract notify_console_match (pattern, match)
```

```
__abstractmethods__ = frozenset({'get_console_matches', 'notify_console_match'})
```

```
__dict__ = mappingproxy({'__module__': 'labgrid.protocol.consoleprotocol', 'get_co
```

```
__module__ = 'labgrid.protocol.consoleprotocol'
```

```

    __weakref__
        list of weak references to the object (if defined)

__abstractmethods__ = frozenset({'read', 'write'})

__dict__ = mappingproxy({'__module__': 'labgrid.protocol.consoleprotocol', '__doc__':
__module__ = 'labgrid.protocol.consoleprotocol'

__weakref__
    list of weak references to the object (if defined)

```

labgrid.protocol.digitaloutputprotocol module

```

class labgrid.protocol.digitaloutputprotocol.DigitalOutputProtocol
    Bases: abc.ABC

```

Abstract class providing the OneWireProtocol interface

```

abstract get ()
    Implementations should return the status of the OneWirePort.

```

```

abstract set (status)
    Implementations should set the status of the OneWirePort

```

```

__abstractmethods__ = frozenset({'get', 'set'})

__dict__ = mappingproxy({'__module__': 'labgrid.protocol.digitaloutputprotocol', '__d
__module__ = 'labgrid.protocol.digitaloutputprotocol'

__weakref__
    list of weak references to the object (if defined)

```

labgrid.protocol.filesystemprotocol module

```

class labgrid.protocol.filesystemprotocol.FileSystemProtocol
    Bases: abc.ABC

```

```

abstract read (filename: str)

```

```

abstract write (filename: str, data: bytes, append: bool)

```

```

__abstractmethods__ = frozenset({'read', 'write'})

__dict__ = mappingproxy({'__module__': 'labgrid.protocol.filesystemprotocol', 'read':
__module__ = 'labgrid.protocol.filesystemprotocol'

__weakref__
    list of weak references to the object (if defined)

```

labgrid.protocol.filetransferprotocol module

```

class labgrid.protocol.filetransferprotocol.FileTransferProtocol
    Bases: abc.ABC

```

```

abstract put (filename: str, remotepath: str)

```

```

abstract get (filename: str, destination: str)

```

```
__abstractmethods__ = frozenset({'get', 'put'})
__dict__ = mappingproxy({'__module__': 'labgrid.protocol.filetransferprotocol', 'put':
__module__ = 'labgrid.protocol.filetransferprotocol'
__weakref__
    list of weak references to the object (if defined)
```

labgrid.protocol.infoprotocol module

```
class labgrid.protocol.infoprotocol.InfoProtocol
    Bases: abc.ABC

    Abstract class providing the InfoProtocol interface

    abstract get_ip(interface: str = 'eth0')
        Implementations should return the IP-adress for the supplied interface.

    abstract get_hostname()
        Implementations should return the hostname for the supplied interface.

    abstract get_service_status(service)
        Implementations should return the status of a service

    __abstractmethods__ = frozenset({'get_hostname', 'get_ip', 'get_service_status'})
    __dict__ = mappingproxy({'__module__': 'labgrid.protocol.infoprotocol', '__doc__': '
    __module__ = 'labgrid.protocol.infoprotocol'
    __weakref__
        list of weak references to the object (if defined)
```

labgrid.protocol.linuxbootprotocol module

```
class labgrid.protocol.linuxbootprotocol.LinuxBootProtocol
    Bases: abc.ABC

    abstract boot(name: str)

    abstract await_boot()

    abstract reset()

    __abstractmethods__ = frozenset({'await_boot', 'boot', 'reset'})
    __dict__ = mappingproxy({'__module__': 'labgrid.protocol.linuxbootprotocol', 'boot':
    __module__ = 'labgrid.protocol.linuxbootprotocol'
    __weakref__
        list of weak references to the object (if defined)
```

labgrid.protocol.mmioprotocol module

```
class labgrid.protocol.mmioprotocol.MMIOProtocol
    Bases: abc.ABC

    abstract read(address: int, size: int, count: int) → bytes
```

```

abstract write (address: int, size: int, data: bytes) → None
__abstractmethods__ = frozenset({'read', 'write'})
__dict__ = mappingproxy({'__module__': 'labgrid.protocol.mmioprotocol', 'read': <fun
__module__ = 'labgrid.protocol.mmioprotocol'
__weakref__
    list of weak references to the object (if defined)

```

labgrid.protocol.powerprotocol module

```

class labgrid.protocol.powerprotocol.PowerProtocol
    Bases: abc.ABC

    abstract on()
    abstract off()
    abstract cycle()
    __abstractmethods__ = frozenset({'cycle', 'off', 'on'})
    __dict__ = mappingproxy({'__module__': 'labgrid.protocol.powerprotocol', 'on': <func
    __module__ = 'labgrid.protocol.powerprotocol'
    __weakref__
        list of weak references to the object (if defined)

```

labgrid.protocol.resetprotocol module

```

class labgrid.protocol.resetprotocol.ResetProtocol
    Bases: abc.ABC

    abstract reset()
    __abstractmethods__ = frozenset({'reset'})
    __dict__ = mappingproxy({'__module__': 'labgrid.protocol.resetprotocol', 'reset': <f
    __module__ = 'labgrid.protocol.resetprotocol'
    __weakref__
        list of weak references to the object (if defined)

```

labgrid.provider package

Submodules

labgrid.provider.fileprovider module

```

class labgrid.provider.fileprovider.FileProvider
    Bases: abc.ABC

    Abstract class for the FileProvider

    abstract get (name: str) → dict
        Get a dictionary of target paths to local paths for a given name.

```

```
abstract list ()
    Get a list of names.

__abstractmethods__ = frozenset({'get', 'list'})

__dict__ = mappingproxy({'__module__': 'labgrid.provider.fileprovider', '__doc__': 'labgrid.provider.fileprovider'})

__module__ = 'labgrid.provider.fileprovider'

__weakref__
    list of weak references to the object (if defined)
```

labgrid.provider.mediafileprovider module

```
class labgrid.provider.mediafileprovider.MediaFileProvider (groups={})
    Bases: labgrid.provider.fileprovider.FileProvider

    get (name)
        Get a dictionary of target paths to local paths for a given name.

    list ()
        Get a list of names.

    __abstractmethods__ = frozenset({})

    __attrs_attrs__ = (Attribute(name='groups', default={}, validator=<instance of validator function>),)

    __init__ (groups={}) → None
        Method generated by attrs for class MediaFileProvider.

    __module__ = 'labgrid.provider.mediafileprovider'

    __repr__ ()
        Method generated by attrs for class MediaFileProvider.
```

labgrid.pytestplugin package

Submodules

labgrid.pytestplugin.fixtures module

```
labgrid.pytestplugin.fixtures.pytest_addoption (parser)

labgrid.pytestplugin.fixtures.env (request, record_testsuite_property)
    Return the environment configured in the supplied configuration file. It contains the targets contained in the configuration file.

labgrid.pytestplugin.fixtures.target (env)
    Return the default target main configured in the supplied configuration file.

labgrid.pytestplugin.fixtures.strategy (request, target)
    Return the Strategy of the default target main configured in the supplied configuration file.
```

labgrid.pytestplugin.hooks module

```
labgrid.pytestplugin.hooks.pytest_configure (config)
```


labgrid.pytestplugin.hooks.**pytest_collection_modifyitems** (*config, items*)

This function matches function feature flags with those found in the environment and disables the item if no match is found

labgrid.pytestplugin.reporter module

labgrid.pytestplugin.reporter.**safe_dupfile** (*f*)

class labgrid.pytestplugin.reporter.**StepReporter** (*terminalreporter, *, rewrite=False*)

Bases: object

__init__ (*terminalreporter, *, rewrite=False*)

Initialize self. See help(type(self)) for accurate signature.

notify (*event*)

pytest_runtest_logstart ()

pytest_runtest_logreport (*report*)

__dict__ = mappingproxy({'__module__': 'labgrid.pytestplugin.reporter', '__init__':

__module__ = 'labgrid.pytestplugin.reporter'

__weakref__

list of weak references to the object (if defined)

class labgrid.pytestplugin.reporter.**ColoredStepReporter** (*terminalreporter, *, rewrite=False*)

Bases: *labgrid.pytestplugin.reporter.StepReporter*

EVENT_COLORS_DARK = {'cycle\$|on\$|off\$': 246, 'expect\$': 8, 'run': 10, 'state_': 51

EVENT_COLORS_LIGHT = {'cycle\$|on\$|off\$': 8, 'expect\$': 250, 'run': 10, 'state_': 5

__init__ (*terminalreporter, *, rewrite=False*)

Initialize self. See help(type(self)) for accurate signature.

__module__ = 'labgrid.pytestplugin.reporter'

labgrid.remote package

Submodules

labgrid.remote.authenticator module

labgrid.remote.client module

The remote.client module contains the functionality to connect to a coordinator, acquire a place and interact with the connected resources

exception labgrid.remote.client.**Error**

Bases: Exception

__module__ = 'labgrid.remote.client'

__weakref__

list of weak references to the object (if defined)

```
exception labgrid.remote.client.UserError
    Bases: labgrid.remote.client.Error

    __module__ = 'labgrid.remote.client'

exception labgrid.remote.client.ServerError
    Bases: labgrid.remote.client.Error

    __module__ = 'labgrid.remote.client'

labgrid.remote.client.start_session(url, realm, extra)
labgrid.remote.client.find_role_by_place(config, place)
labgrid.remote.client.find_any_role_with_place(config)
labgrid.remote.client.main()
```

labgrid.remote.common module

```
class labgrid.remote.common.ResourceEntry(data)
    Bases: object

    __attrs_post_init__()

    property acquired
    property avail
    property cls
    property params
    property args
        arguments for resource construction
    property extra
        extra resource information

    asdict()
    update(data)
        apply updated information from the exporter on the coordinator
    acquire(place_name)
    release()

    __attrs_attrs__ = (Attribute(name='data', default=NOTHING, validator=None, repr=True,
    __dict__ = mappingproxy({'__module__': 'labgrid.remote.common', '__attrs_post_init__'
    __init__(data) → None
        Method generated by attrs for class ResourceEntry.
    __module__ = 'labgrid.remote.common'
    __repr__()
        Method generated by attrs for class ResourceEntry.
    __weakref__
        list of weak references to the object (if defined)

class labgrid.remote.common.ResourceMatch(exporter, group, cls, name=None, re-
    name=None)
    Bases: object
```

```

classmethod fromstr (pattern)

__repr__ ()
    Return repr(self).

__str__ ()
    Return str(self).

ismatch (resource_path)
    Return True if this matches the given resource

__attrs_attrs__ = (Attribute(name='exporter', default=NOTHING, validator=None, repr=Tr
__dict__ = mappingproxy({'__module__': 'labgrid.remote.common', 'fromstr': <classmet
__eq__ (other)
    Method generated by attrs for class ResourceMatch.

__ge__ (other)
    Method generated by attrs for class ResourceMatch.

__gt__ (other)
    Method generated by attrs for class ResourceMatch.

__hash__ = None

__init__ (exporter, group, cls, name=None, rename=None) → None
    Method generated by attrs for class ResourceMatch.

__le__ (other)
    Method generated by attrs for class ResourceMatch.

__lt__ (other)
    Method generated by attrs for class ResourceMatch.

__module__ = 'labgrid.remote.common'

__ne__ (other)
    Method generated by attrs for class ResourceMatch.

__weakref__
    list of weak references to the object (if defined)

class labgrid.remote.common.Place (name, aliases=NOTHING, comment="", tags=NOTHING,
                                     matches=NOTHING, acquired=None, ac-
                                     quired_resources=NOTHING, allowed=NOTHING, cre-
                                     ated=NOTHING, changed=NOTHING, reservation=None)

Bases: object

asdict ()

update (config)

show (level=0)

getmatch (resource_path)
    Return the ResourceMatch object for the given resource path or None if not found.

    A resource_path has the structure (exporter, group, cls, name).

hasmatch (resource_path)
    Return True if this place as a ResourceMatch object for the given resource path.

    A resource_path has the structure (exporter, group, cls, name).

touch ()

```

```
__attrs_attrs__ = (Attribute(name='name', default=NOTHING, validator=None, repr=True,
__dict__ = mappingproxy({'__module__': 'labgrid.remote.common', 'asdict': <function
__init__(name, aliases=NOTHING, comment="", tags=NOTHING, matches=NOTHING, ac-
quired=None, acquired_resources=NOTHING, allowed=NOTHING, created=NOTHING,
changed=NOTHING, reservation=None) → None
    Method generated by attrs for class Place.

__module__ = 'labgrid.remote.common'

__repr__ ()
    Method generated by attrs for class Place.

__weakref__
    list of weak references to the object (if defined)

class labgrid.remote.common.ReservationState
    Bases: enum.Enum

    An enumeration.

    waiting = 0
    allocated = 1
    acquired = 2
    expired = 3
    invalid = 4

    __module__ = 'labgrid.remote.common'

class labgrid.remote.common.Reservation(owner, token=NOTHING, state='waiting',
prio=0.0, filters=NOTHING, allocations=NOTHING, created=NOTHING, time-
out=NOTHING)

    Bases: object

    asdict ()

    refresh (delta=60)

    property expired

    show (level=0)

    __attrs_attrs__ = (Attribute(name='owner', default=NOTHING, validator=<instance_of val
__dict__ = mappingproxy({'__module__': 'labgrid.remote.common', 'asdict': <function
__init__(owner, token=NOTHING, state='waiting', prio=0.0, filters=NOTHING, alloca-
tions=NOTHING, created=NOTHING, timeout=NOTHING) → None
    Method generated by attrs for class Reservation.

    __module__ = 'labgrid.remote.common'

    __repr__ ()
        Method generated by attrs for class Reservation.

    __weakref__
        list of weak references to the object (if defined)

labgrid.remote.common.enable_tcp_nodelay (session)
    asyncio/autobahn does not set TCP_NODELAY by default, so we need to do it like this for now.
```

labgrid.remote.config module

```

class labgrid.remote.config.ResourceConfig(filename)
    Bases: object

    __attrs_post_init__()

    __attrs_attrs__ = (Attribute(name='filename', default=NOTHING, validator=<instance_of '
    __dict__ = mappingproxy({'__module__': 'labgrid.remote.config', '__attrs_post_init__'
    __init__(filename) → None
        Method generated by attrs for class ResourceConfig.

    __module__ = 'labgrid.remote.config'

    __repr__()
        Method generated by attrs for class ResourceConfig.

    __weakref__
        list of weak references to the object (if defined)

```

labgrid.remote.coordinator module

The coordinator module coordinates exported resources and clients accessing them.

```

class labgrid.remote.coordinator.Action
    Bases: enum.Enum

    An enumeration.

    ADD = 0
    DEL = 1
    UPD = 2

    __module__ = 'labgrid.remote.coordinator'

class labgrid.remote.coordinator.RemoteSession
    Bases: object

    class encapsulating a session, used by ExporterSession and ClientSession

    property key
        Key of the session

    property name
        Name of the session

    __attrs_attrs__ = (Attribute(name='coordinator', default=NOTHING, validator=None, repr
    __attrs_init__(coordinator, session, authid) → None
        Method generated by attrs for class RemoteSession.

    __dict__ = mappingproxy({'__module__': 'labgrid.remote.coordinator', '__doc__': 'cla
    __module__ = 'labgrid.remote.coordinator'

    __repr__()
        Method generated by attrs for class RemoteSession.

    __weakref__
        list of weak references to the object (if defined)

```

```
class labgrid.remote.coordinator.ExporterSession (coordinator, session, authid)
```

Bases: `labgrid.remote.coordinator.RemoteSession`

An ExporterSession is opened for each Exporter connecting to the coordinator, allowing the Exporter to get and set resources

```
set_resource (groupname, resourcename, resourcedata)
```

```
get_resources ()
```

Method invoked by the client, get the resources from the coordinator

```
__attrs_attrs__ = (Attribute(name='coordinator', default=NOTHING, validator=None, repr=
```

```
__init__ (coordinator, session, authid) → None
```

Method generated by attrs for class ExporterSession.

```
__module__ = 'labgrid.remote.coordinator'
```

```
__repr__ ()
```

Method generated by attrs for class ExporterSession.

```
class labgrid.remote.coordinator.ClientSession (coordinator, session, authid)
```

Bases: `labgrid.remote.coordinator.RemoteSession`

```
__attrs_attrs__ = (Attribute(name='coordinator', default=NOTHING, validator=None, repr=
```

```
__init__ (coordinator, session, authid) → None
```

Method generated by attrs for class ClientSession.

```
__module__ = 'labgrid.remote.coordinator'
```

```
__repr__ ()
```

Method generated by attrs for class ClientSession.

```
class labgrid.remote.coordinator.ResourceImport (data, *, path)
```

Bases: `labgrid.remote.common.ResourceEntry`

Represents a local resource exported from an exporter.

The ResourceEntry attributes contain the information for the client.

```
__attrs_attrs__ = (Attribute(name='data', default=NOTHING, validator=None, repr=True, c
```

```
__init__ (data, *, path) → None
```

Method generated by attrs for class ResourceImport.

```
__module__ = 'labgrid.remote.coordinator'
```

```
__repr__ ()
```

Method generated by attrs for class ResourceImport.

```
labgrid.remote.coordinator.locked (func)
```

labgrid.remote.exporter module

The remote.exporter module exports resources to the coordinator and makes them available to other clients on the same coordinator

```
exception labgrid.remote.exporter.ExporterError
```

Bases: `Exception`

```
__module__ = 'labgrid.remote.exporter'
```

```

__weakref__
    list of weak references to the object (if defined)

exception labgrid.remote.exporter.BrokenResourceError
    Bases: labgrid.remote.exporter.ExporterError

__module__ = 'labgrid.remote.exporter'

labgrid.remote.exporter.log_subprocess_kernel_stack(logger, child)

class labgrid.remote.exporter.ResourceExport(data, host='build-13763032-project-82349-labgrid', proxy=None, proxy_required=False)
    Bases: labgrid.remote.common.ResourceEntry
    Represents a local resource exported via a specific protocol.
    The ResourceEntry attributes contain the information for the client.
    __attrs_post_init__()
    property broken
    start()
    stop()
    poll()
    acquire(*args, **kwargs)
    release(*args, **kwargs)
    __attrs_attrs__ = (Attribute(name='data', default=NOTHING, validator=None, repr=True,
    __init__(data, host='build-13763032-project-82349-labgrid', proxy=None, proxy_required=False)
        → None
        Method generated by attrs for class ResourceExport.
    __module__ = 'labgrid.remote.exporter'
    __repr__()
        Method generated by attrs for class ResourceExport.

class labgrid.remote.exporter.SerialPortExport(data, host='build-13763032-project-82349-labgrid', proxy=None, proxy_required=False)
    Bases: labgrid.remote.exporter.ResourceExport
    ResourceExport for a USB or Raw SerialPort
    __attrs_post_init__()
    __del__()
    __attrs_attrs__ = (Attribute(name='data', default=NOTHING, validator=None, repr=True,
    __init__(data, host='build-13763032-project-82349-labgrid', proxy=None, proxy_required=False)
        → None
        Method generated by attrs for class SerialPortExport.
    __module__ = 'labgrid.remote.exporter'
    __repr__()
        Method generated by attrs for class SerialPortExport.

```

```
class labgrid.remote.exporter.USBEthernetExport (data, host='build-13763032-project-82349-labgrid', proxy=None, proxy_required=False)
```

Bases: *labgrid.remote.exporter.ResourceExport*

ResourceExport for a USB ethernet interface

```
__attrs_post_init__()
```

```
__attrs_attrs__ = (Attribute(name='data', default=NOTHING, validator=None, repr=True, o
```

```
__init__ (data, host='build-13763032-project-82349-labgrid', proxy=None, proxy_required=False)
    → None
```

Method generated by attrs for class USBEthernetExport.

```
__module__ = 'labgrid.remote.exporter'
```

```
__repr__()
```

Method generated by attrs for class USBEthernetExport.

```
class labgrid.remote.exporter.USBGenericExport (data, host='build-13763032-project-82349-labgrid', proxy=None, proxy_required=False)
```

Bases: *labgrid.remote.exporter.ResourceExport*

ResourceExport for USB devices accessed directly from userspace

```
__attrs_post_init__()
```

```
__attrs_attrs__ = (Attribute(name='data', default=NOTHING, validator=None, repr=True, o
```

```
__init__ (data, host='build-13763032-project-82349-labgrid', proxy=None, proxy_required=False)
    → None
```

Method generated by attrs for class USBGenericExport.

```
__module__ = 'labgrid.remote.exporter'
```

```
__repr__()
```

Method generated by attrs for class USBGenericExport.

```
class labgrid.remote.exporter.USBSigrokExport (data, host='build-13763032-project-82349-labgrid', proxy=None, proxy_required=False)
```

Bases: *labgrid.remote.exporter.USBGenericExport*

ResourceExport for USB devices accessed directly from userspace

```
__attrs_post_init__()
```

```
__attrs_attrs__ = (Attribute(name='data', default=NOTHING, validator=None, repr=True, o
```

```
__init__ (data, host='build-13763032-project-82349-labgrid', proxy=None, proxy_required=False)
    → None
```

Method generated by attrs for class USBSigrokExport.

```
__module__ = 'labgrid.remote.exporter'
```

```
__repr__()
```

Method generated by attrs for class USBSigrokExport.

```
class labgrid.remote.exporter.USBSDMuxExport (data, host='build-13763032-project-82349-labgrid', proxy=None, proxy_required=False)
```

Bases: *labgrid.remote.exporter.USBGenericExport*

ResourceExport for USB devices accessed directly from userspace


```

__attrs_post_init__()

__attrs_attrs__ = (Attribute(name='data', default=NOTHING, validator=None, repr=True, c
__init__(data, host='build-13763032-project-82349-labgrid', proxy=None, proxy_required=False)
    → None
    Method generated by attrs for class USBSDMuxExport.

__module__ = 'labgrid.remote.exporter'

__repr__()
    Method generated by attrs for class USBSDMuxExport.

class labgrid.remote.exporter.USBSDWireExport(data, host='build-13763032-project-
82349-labgrid', proxy=None,
proxy_required=False)

Bases: labgrid.remote.exporter.USBGenericExport
ResourceExport for USB devices accessed directly from userspace

__attrs_post_init__()

__attrs_attrs__ = (Attribute(name='data', default=NOTHING, validator=None, repr=True, c
__init__(data, host='build-13763032-project-82349-labgrid', proxy=None, proxy_required=False)
    → None
    Method generated by attrs for class USBSDWireExport.

__module__ = 'labgrid.remote.exporter'

__repr__()
    Method generated by attrs for class USBSDWireExport.

class labgrid.remote.exporter.SiSPMPowerPortExport(data, host='build-
13763032-project-82349-
labgrid', proxy=None,
proxy_required=False)

Bases: labgrid.remote.exporter.USBGenericExport
ResourceExport for ports on GEMBRID switches

__attrs_post_init__()

__attrs_attrs__ = (Attribute(name='data', default=NOTHING, validator=None, repr=True, c
__init__(data, host='build-13763032-project-82349-labgrid', proxy=None, proxy_required=False)
    → None
    Method generated by attrs for class SiSPMPowerPortExport.

__module__ = 'labgrid.remote.exporter'

__repr__()
    Method generated by attrs for class SiSPMPowerPortExport.

class labgrid.remote.exporter.USBPowerPortExport(data, host='build-13763032-project-
82349-labgrid', proxy=None,
proxy_required=False)

Bases: labgrid.remote.exporter.USBGenericExport
ResourceExport for ports on switchable USB hubs

__attrs_post_init__()

__attrs_attrs__ = (Attribute(name='data', default=NOTHING, validator=None, repr=True, c

```

```
__init__ (data, host='build-13763032-project-82349-labgrid', proxy=None, proxy_required=False)
    → None
    Method generated by attrs for class USBPowerPortExport.

__module__ = 'labgrid.remote.exporter'

__repr__ ()
    Method generated by attrs for class USBPowerPortExport.

class labgrid.remote.exporter.USBDeDitecRelaisExport (data, host='build-
    13763032-project-82349-
    labgrid', proxy=None,
    proxy_required=False)

Bases: labgrid.remote.exporter.USBGenericExport
ResourceExport for outputs on deditec relais

__attrs_post_init__ ()

__attrs_attrs__ = (Attribute(name='data', default=NOTHING, validator=None, repr=True, o
__init__ (data, host='build-13763032-project-82349-labgrid', proxy=None, proxy_required=False)
    → None
    Method generated by attrs for class USBDeDitecRelaisExport.

__module__ = 'labgrid.remote.exporter'

__repr__ ()
    Method generated by attrs for class USBDeDitecRelaisExport.

class labgrid.remote.exporter.EthernetPortExport (data, host='build-13763032-project-
    82349-labgrid', proxy=None,
    proxy_required=False)

Bases: labgrid.remote.exporter.ResourceExport
ResourceExport for a ethernet interface

__attrs_post_init__ ()

__attrs_attrs__ = (Attribute(name='data', default=NOTHING, validator=None, repr=True, o
__eq__ (other)
    Method generated by attrs for class EthernetPortExport.

__ge__ (other)
    Method generated by attrs for class EthernetPortExport.

__gt__ (other)
    Method generated by attrs for class EthernetPortExport.

__hash__ = None

__init__ (data, host='build-13763032-project-82349-labgrid', proxy=None, proxy_required=False)
    → None
    Method generated by attrs for class EthernetPortExport.

__le__ (other)
    Method generated by attrs for class EthernetPortExport.

__lt__ (other)
    Method generated by attrs for class EthernetPortExport.

__module__ = 'labgrid.remote.exporter'

__ne__ (other)
    Method generated by attrs for class EthernetPortExport.
```

```

__repr__()
    Method generated by attrs for class EthernetPortExport.
class labgrid.remote.exporter.GPIOGenericExport (data, host='build-13763032-project-
                                                    82349-labgrid', proxy=None,
                                                    proxy_required=False)
Bases: labgrid.remote.exporter.ResourceExport
ResourceExport for GPIO lines accessed directly from userspace
__attrs_post_init__()
__attrs_attrs__ = (Attribute(name='data', default=NOTHING, validator=None, repr=True,
__init__(data, host='build-13763032-project-82349-labgrid', proxy=None, proxy_required=False)
    → None
    Method generated by attrs for class GPIOGenericExport.
__module__ = 'labgrid.remote.exporter'
__repr__()
    Method generated by attrs for class GPIOGenericExport.
class labgrid.remote.exporter.NetworkServiceExport (data, host='build-
                                                    13763032-project-82349-
                                                    labgrid', proxy=None,
                                                    proxy_required=False)
Bases: labgrid.remote.exporter.ResourceExport
ResourceExport for a NetworkService
This checks if the address has a interface suffix and then provides the neccessary proxy information.
__attrs_post_init__()
__attrs_attrs__ = (Attribute(name='data', default=NOTHING, validator=None, repr=True,
__eq__(other)
    Method generated by attrs for class NetworkServiceExport.
__ge__(other)
    Method generated by attrs for class NetworkServiceExport.
__gt__(other)
    Method generated by attrs for class NetworkServiceExport.
__hash__ = None
__init__(data, host='build-13763032-project-82349-labgrid', proxy=None, proxy_required=False)
    → None
    Method generated by attrs for class NetworkServiceExport.
__le__(other)
    Method generated by attrs for class NetworkServiceExport.
__lt__(other)
    Method generated by attrs for class NetworkServiceExport.
__module__ = 'labgrid.remote.exporter'
__ne__(other)
    Method generated by attrs for class NetworkServiceExport.
__repr__()
    Method generated by attrs for class NetworkServiceExport.

```

```
class labgrid.remote.exporter.LXAIOBusNodeExport (data, host='build-13763032-project-82349-labgrid', proxy=None, proxy_required=False)
```

Bases: `labgrid.remote.exporter.ResourceExport`

ResourceExport for LXAIOBusNode devices accessed via the HTTP API

```
__attrs_post_init__()
```

```
__attrs_attrs__ = (Attribute(name='data', default=NOTHING, validator=None, repr=True, ...)
```

```
__init__ (data, host='build-13763032-project-82349-labgrid', proxy=None, proxy_required=False)
    → None
```

Method generated by attrs for class LXAIOBusNodeExport.

```
__module__ = 'labgrid.remote.exporter'
```

```
__repr__()
```

Method generated by attrs for class LXAIOBusNodeExport.

```
labgrid.remote.exporter.main()
```

labgrid.remote.scheduler module

```
class labgrid.remote.scheduler.TagSet (name, tags)
```

Bases: `object`

```
__attrs_attrs__ = (Attribute(name='name', default=NOTHING, validator=<instance_of vali
```

```
__dict__ = mappingproxy({'__module__': 'labgrid.remote.scheduler', '__dict__': <attr
```

```
__init__ (name, tags) → None
```

Method generated by attrs for class TagSet.

```
__module__ = 'labgrid.remote.scheduler'
```

```
__repr__()
```

Method generated by attrs for class TagSet.

```
__weakref__
```

list of weak references to the object (if defined)

```
labgrid.remote.scheduler.schedule_step (places, filters)
```

Find the filters that can be directly allocated without overlap.

```
labgrid.remote.scheduler.schedule_overlaps (places, filters)
```

Iterate `schedule_step` until no more allocations are found.

```
labgrid.remote.scheduler.schedule (places, filters)
```

labgrid.resource package

Submodules

labgrid.resource.base module

```
class labgrid.resource.base.SerialPort (target, name, port=None, speed=115200)
```

Bases: `labgrid.resource.common.Resource`

The basic SerialPort describes port and speed

Parameters

- **port** (*str*) – port to connect to
- **speed** (*int*) – speed of the port, defaults to 115200

__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True

__init__ (*target, name, port=None, speed=115200*) → None
Method generated by attrs for class SerialPort.

__module__ = 'labgrid.resource.base'

__repr__ ()
Method generated by attrs for class SerialPort.

class labgrid.resource.base.**EthernetInterface** (*target, name, ifname=None*)

Bases: [labgrid.resource.common.Resource](#)

The basic EthernetInterface contains an interfacename

Parameters **ifname** (*str*) – name of the interface

__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True

__init__ (*target, name, ifname=None*) → None
Method generated by attrs for class EthernetInterface.

__module__ = 'labgrid.resource.base'

__repr__ ()
Method generated by attrs for class EthernetInterface.

class labgrid.resource.base.**EthernetPort** (*target, name, switch=None, interface=None*)

Bases: [labgrid.resource.common.Resource](#)

The basic EthernetPort describes a switch and interface

Parameters

- **switch** (*str*) – name of the switch
- **interface** (*str*) – name of the interface

__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True

__eq__ (*other*)
Method generated by attrs for class EthernetPort.

__ge__ (*other*)
Method generated by attrs for class EthernetPort.

__gt__ (*other*)
Method generated by attrs for class EthernetPort.

__hash__ = None

__init__ (*target, name, switch=None, interface=None*) → None
Method generated by attrs for class EthernetPort.

__le__ (*other*)
Method generated by attrs for class EthernetPort.

__lt__ (*other*)
Method generated by attrs for class EthernetPort.

__module__ = 'labgrid.resource.base'

`__ne__` (*other*)

Method generated by attrs for class EthernetPort.

`__repr__` ()

Method generated by attrs for class EthernetPort.

class labgrid.resource.base.SysfsGPIO (*target, name, index=None*)

Bases: *labgrid.resource.common.Resource*

The basic SysfsGPIO contains an index

Parameters *index* (*int*) – index of target gpio line.

`__attrs_attrs__` = (**Attribute**(name='target', default=NOTHING, validator=None, repr=True

`__init__` (*target, name, index=None*) → None

Method generated by attrs for class SysfsGPIO.

`__module__` = 'labgrid.resource.base'

`__repr__` ()

Method generated by attrs for class SysfsGPIO.

labgrid.resource.common module

class labgrid.resource.common.Resource (*target, name*)

Bases: *labgrid.binding.BindingMixin*

Represents a resource which is used by drivers. It only stores information and does not implement any actual functionality.

Resources can exist without a target, but they must be bound to one before use.

Life cycle:

- create
- bind (n times)

`__attrs_post_init__` ()

property `command_prefix`

property `parent`

get_managed_parent ()

For Resources which have been created at runtime, return the ManagedResource resource which created it.

Returns None otherwise.

poll ()

`__attrs_attrs__` = (**Attribute**(name='target', default=NOTHING, validator=None, repr=True

`__init__` (*target, name*) → None

Method generated by attrs for class Resource.

`__module__` = 'labgrid.resource.common'

`__repr__` ()

Method generated by attrs for class Resource.

```
class labgrid.resource.common.NetworkResource (target, name, host)
```

Bases: [labgrid.resource.common.Resource](#)

Represents a remote Resource available on another computer.

This stores a `command_prefix` to describe how to connect to the remote computer.

Parameters `host` (*str*) – remote host the resource is available on

property `command_prefix`

```
__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True
```

```
__init__ (target, name, host) → None
```

Method generated by attrs for class NetworkResource.

```
__module__ = 'labgrid.resource.common'
```

```
__repr__ ()
```

Method generated by attrs for class NetworkResource.

```
class labgrid.resource.common.ResourceManager
```

Bases: `object`

```
instances = {}
```

```
classmethod get ()
```

```
__attrs_post_init__ ()
```

```
on_resource_added (resource)
```

```
poll ()
```

```
__attrs_attrs__ = ()
```

```
__dict__ = mappingproxy({'__module__': 'labgrid.resource.common', 'instances': {}, 'o
```

```
__init__ () → None
```

Method generated by attrs for class ResourceManager.

```
__module__ = 'labgrid.resource.common'
```

```
__repr__ ()
```

Method generated by attrs for class ResourceManager.

```
__weakref__
```

list of weak references to the object (if defined)

```
class labgrid.resource.common.ManagedResource (target, name)
```

Bases: [labgrid.resource.common.Resource](#)

Represents a resource which can appear and disappear at runtime. Every ManagedResource has a corresponding ResourceManager which handles these events.

```
manager_cls
```

alias of [ResourceManager](#)

```
__attrs_post_init__ ()
```

```
poll ()
```

```
__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True
```

```
__init__ (target, name) → None
```

Method generated by attrs for class ManagedResource.

```
__module__ = 'labgrid.resource.common'
```

`__repr__()`

Method generated by attrs for class ManagedResource.

`get_managed_parent()`

For Resources which have been created at runtime, return the ManagedResource resource which created it.

Returns None otherwise.

labgrid.resource.docker module

Auxiliary classes that assist DockerDriver. Specifically, DockerDaemon and DockerManager will create the NetworkResource instance that is declared in the specification (e.g. yaml) of DockerDriver.

class `labgrid.resource.docker.DockerConstants`

Bases: `object`

Class constants for handling container cleanup

`DOCKER_LG_CLEANUP_LABEL = 'lg_cleanup'`

`DOCKER_LG_CLEANUP_TYPE_AUTO = 'auto'`

`__dict__ = mappingproxy({'__module__': 'labgrid.resource.docker', '__doc__': 'Class`

`__module__ = 'labgrid.resource.docker'`

`__weakref__`

list of weak references to the object (if defined)

class `labgrid.resource.docker.DockerManager`

Bases: `labgrid.resource.common.ResourceManager`

The DockerManager is responsible for cleaning up dangling containers and managing the managed Network-Service resources. Different docker daemons for different targets are allowed, but there has to be only one for each target.

`__attrs_post_init__()`

`on_resource_added(resource)`

If the resource added is a DockerDaemon, make sure this is the only one added for this target. If it is, create a docker client to be used to communicate with the docker daemon.

`poll()`

Ask associated DockerDaemon resource to check if associated NetworkService has come up.

`__attrs_attrs__ = ()`

`__init__()` → None

Method generated by attrs for class DockerManager.

`__module__ = 'labgrid.resource.docker'`

`__repr__()`

Method generated by attrs for class DockerManager.

class `labgrid.resource.docker.DockerDaemon(target, name, docker_daemon_url)`

Bases: `labgrid.resource.common.ManagedResource`

A resource identifying a docker daemon

`docker_daemon_url = None`

The docker network service is a managed resource mapping a container name to a network service.


```

manager_cls
    alias of DockerManager

__attrs_post_init__()

on_client_bound(client)
    Each time a docker driver binds to the DockerDaemon resource the docker driver network services list
    is iterated and for each network service defined a NetworkService resource instance is created with the
    parameters from the configuration file.

on_poll(docker_client)
    Check if associated NetworkService has come up.

__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True
__init__(target, name, docker_daemon_url) → None
    Method generated by attrs for class DockerDaemon.

__module__ = 'labgrid.resource.docker'

__repr__()
    Method generated by attrs for class DockerDaemon.

```

labgrid.resource.ethernetport module

```

class labgrid.resource.ethernetport.SNMPSwitch(hostname)
    Bases: object

    SNMPSwitch describes a switch accessible over SNMP. This class implements functions to query ports and the
    forwarding database.

    __attrs_post_init__()

    update()
        Update port status and forwarding database status

        Returns None

    __attrs_attrs__ = (Attribute(name='hostname', default=NOTHING, validator=<instance_of
    __dict__ = mappingproxy({'__module__': 'labgrid.resource.ethernetport', '__doc__': '
    __eq__(other)
        Method generated by attrs for class SNMPSwitch.

    __ge__(other)
        Method generated by attrs for class SNMPSwitch.

    __gt__(other)
        Method generated by attrs for class SNMPSwitch.

    __hash__ = None

    __init__(hostname) → None
        Method generated by attrs for class SNMPSwitch.

    __le__(other)
        Method generated by attrs for class SNMPSwitch.

    __lt__(other)
        Method generated by attrs for class SNMPSwitch.

    __module__ = 'labgrid.resource.ethernetport'

```

`__ne__ (other)`
Method generated by attrs for class SNMPSwitch.

`__repr__ ()`
Method generated by attrs for class SNMPSwitch.

`__weakref__`
list of weak references to the object (if defined)

class `labgrid.resource.ethernetport.EthernetPortManager`
Bases: `labgrid.resource.common.ResourceManager`

The EthernetPortManager periodically polls the switch for new updates.

`__attrs_post_init__ ()`

`on_resource_added (resource)`
Handler to execute when the resource is added
Checks whether the resource can be managed by this Manager and starts the event loop.

Parameters `resource` (`Resource`) – resource to check against

Returns None

`poll ()`
Updates the state with new information from the event loop
Returns None

`__attrs_attrs__ = ()`

`__eq__ (other)`
Method generated by attrs for class EthernetPortManager.

`__ge__ (other)`
Method generated by attrs for class EthernetPortManager.

`__gt__ (other)`
Method generated by attrs for class EthernetPortManager.

`__hash__ = None`

`__init__ ()` → None
Method generated by attrs for class EthernetPortManager.

`__le__ (other)`
Method generated by attrs for class EthernetPortManager.

`__lt__ (other)`
Method generated by attrs for class EthernetPortManager.

`__module__ = 'labgrid.resource.ethernetport'`

`__ne__ (other)`
Method generated by attrs for class EthernetPortManager.

`__repr__ ()`
Method generated by attrs for class EthernetPortManager.

class `labgrid.resource.ethernetport.SNMPEthernetPort` (`target, name, switch, interface`)
Bases: `labgrid.resource.common.ManagedResource`

SNMPEthernetPort describes an ethernet port which can be queried over SNMP.

Parameters

- **switch**(*str*) – hostname of the switch to query
- **interface**(*str*) – name of the interface to query

manager_cls

alias of *EthernetPortManager*

__attrs_post_init__()

__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True

__eq__(*other*)

Method generated by attrs for class SNMPEthernetPort.

__ge__(*other*)

Method generated by attrs for class SNMPEthernetPort.

__gt__(*other*)

Method generated by attrs for class SNMPEthernetPort.

__hash__ = None

__init__(*target, name, switch, interface*) → None

Method generated by attrs for class SNMPEthernetPort.

__le__(*other*)

Method generated by attrs for class SNMPEthernetPort.

__lt__(*other*)

Method generated by attrs for class SNMPEthernetPort.

__module__ = 'labgrid.resource.ethernetport'

__ne__(*other*)

Method generated by attrs for class SNMPEthernetPort.

__repr__()

Method generated by attrs for class SNMPEthernetPort.

labgrid.resource.flashrom module

class labgrid.resource.flashrom.**Flashrom**(*target, name, programmer*)

Bases: *labgrid.resource.common.Resource*

Programmer is the programmer parameter described in man(8) of flashrom

__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True

__init__(*target, name, programmer*) → None

Method generated by attrs for class Flashrom.

__module__ = 'labgrid.resource.flashrom'

__repr__()

Method generated by attrs for class Flashrom.

class labgrid.resource.flashrom.**NetworkFlashrom**(*target, name, host, programmer*)

Bases: *labgrid.resource.common.NetworkResource*

__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True

__init__(*target, name, host, programmer*) → None

Method generated by attrs for class NetworkFlashrom.

```
__module__ = 'labgrid.resource.flashrom'
__repr__ ()
    Method generated by attrs for class NetworkFlashrom.
```

labgrid.resource.lxaibus module

```
class labgrid.resource.lxaibus.LXAIOBusNodeManager
    Bases: labgrid.resource.common.ResourceManager
```

```
__attrs_post_init__ ()
```

```
poll ()
```

```
__attrs_attrs__ = ()
```

```
__init__ () → None
```

Method generated by attrs for class LXAIOBusNodeManager.

```
__module__ = 'labgrid.resource.lxaibus'
```

```
__repr__ ()
```

Method generated by attrs for class LXAIOBusNodeManager.

```
class labgrid.resource.lxaibus.LXAIOBusNode (target, name, host, node)
```

Bases: *labgrid.resource.common.ManagedResource*

This resource describes a generic LXA IO BUs Node.

Parameters

- **host** (*str*) – hostname of the owserver e.g. localhost:4304
- **node** (*str*) – node name e.g. EthMux-5c12ca8b

```
manager_cls
```

alias of *LXAIOBusNodeManager*

```
__attrs_post_init__ ()
```

```
__attrs_attrs__ = (Attribute (name='target', default=NOTHING, validator=None, repr=True
```

```
__init__ (target, name, host, node) → None
```

Method generated by attrs for class LXAIOBusNode.

```
__module__ = 'labgrid.resource.lxaibus'
```

```
__repr__ ()
```

Method generated by attrs for class LXAIOBusNode.

```
class labgrid.resource.lxaibus.LXAIOBusPIO (target, name, host, node, pin, invert=False)
```

Bases: *labgrid.resource.lxaibus.LXAIOBusNode*

This resource describes a LXA IO Bus PIO Port.

Parameters

- **pin** (*str*) – pin label e.g. OUT0
- **invert** (*bool*) – optional, whether the logic level is inverted (active-low)

```
__attrs_attrs__ = (Attribute (name='target', default=NOTHING, validator=None, repr=True
```

```
__init__ (target, name, host, node, pin, invert=False) → None
```

Method generated by attrs for class LXAIOBusPIO.

```
__module__ = 'labgrid.resource.lxaibus'
__repr__ ()
    Method generated by attrs for class LXAIOBusPIO.
```

labgrid.resource.modbus module

```
class labgrid.resource.modbus.ModbusTCPCoil (target, name, host, coil, invert=False)
    Bases: labgrid.resource.common.Resource
```

This resource describes Modbus TCP coil.

Parameters

- **host** (*str*) – hostname of the Modbus TCP server e.g. “192.168.23.42:502”
- **coil** (*int*) – index of the coil e.g. 3
- **invert** (*bool*) – optional, whether the logic level is be inverted (active-low)

```
__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True
__init__ (target, name, host, coil, invert=False) → None
    Method generated by attrs for class ModbusTCPCoil.
__module__ = 'labgrid.resource.modbus'
__repr__ ()
    Method generated by attrs for class ModbusTCPCoil.
```

labgrid.resource.networkservice module

```
class labgrid.resource.networkservice.NetworkService (target, name, address, user-
                                                         name, password=", port=22)
```

Bases: `labgrid.resource.common.Resource`

```
__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True
__init__ (target, name, address, username, password=", port=22) → None
    Method generated by attrs for class NetworkService.
__module__ = 'labgrid.resource.networkservice'
__repr__ ()
    Method generated by attrs for class NetworkService.
```

labgrid.resource.onewirereport module

```
class labgrid.resource.onewirereport.OneWirePIO (target, name, host, path, invert=False)
    Bases: labgrid.resource.common.Resource
```

This resource describes a Onewire PIO Port.

Parameters

- **host** (*str*) – hostname of the owserver e.g. localhost:4304
- **path** (*str*) – path to the port on the owserver e.g. 29.7D6913000000/PIO.0
- **invert** (*bool*) – optional, whether the logic level is be inverted (active-low)

```
__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True)
__init__(target, name, host, path, invert=False) → None
    Method generated by attrs for class OneWirePIO.
__module__ = 'labgrid.resource.onewirepio'
__repr__()
    Method generated by attrs for class OneWirePIO.
```

labgrid.resource.power module

class labgrid.resource.power.**NetworkPowerPort** (*target, name, model, host, index*)

Bases: [labgrid.resource.common.Resource](#)

The NetworkPowerPort describes a remotely switchable PowerPort

Parameters

- **model** (*str*) – model of the external power switch
- **host** (*str*) – host to connect to
- **index** (*str*) – index of the power port on the external switch

```
__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True)
__init__(target, name, model, host, index) → None
    Method generated by attrs for class NetworkPowerPort.
__module__ = 'labgrid.resource.power'
__repr__()
    Method generated by attrs for class NetworkPowerPort.
```

class labgrid.resource.power.**PDUDaemonPort** (*target, name, host, pdu, index*)

Bases: [labgrid.resource.common.Resource](#)

The PDUDaemonPort describes a port on a PDU accessible via PDUDaemon

Parameters

- **host** (*str*) – name of the host running the PDUDaemon
- **pdu** (*str*) – name of the PDU in the configuration file
- **index** (*int*) – index of the power port on the PDU

```
__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True)
__init__(target, name, host, pdu, index) → None
    Method generated by attrs for class PDUDaemonPort.
__module__ = 'labgrid.resource.power'
__repr__()
    Method generated by attrs for class PDUDaemonPort.
```

labgrid.resource.pyvisa module

class labgrid.resource.pyvisa.**PyVISADevice** (*target, name, type, url*)

Bases: [labgrid.resource.common.Resource](#)

The PyVISADevice describes a test stimuli device controlled with PyVISA

Parameters

- **type** (*str*) – device resource type following the pyVISA resource syntax, e.g. ASRL, TCPIP...
- **url** (*str*) – device identifier on selected resource, e.g. <ip> for TCPIP resource

__attrs_attrs__ = (**Attribute**(name='target', default=NOTHING, validator=None, repr=True

__init__ (*target, name, type, url*) → None

Method generated by attrs for class PyVISADevice.

__module__ = 'labgrid.resource.pyvisa'

__repr__ ()

Method generated by attrs for class PyVISADevice.

labgrid.resource.remote module

class labgrid.resource.remote.RemotePlaceManager

Bases: *labgrid.resource.common.ResourceManager*

__attrs_post_init__ ()

on_resource_added (*resource*)

poll ()

__attrs_attrs__ = ()

__init__ () → None

Method generated by attrs for class RemotePlaceManager.

__module__ = 'labgrid.resource.remote'

__repr__ ()

Method generated by attrs for class RemotePlaceManager.

class labgrid.resource.remote.RemotePlace (*target, name*)

Bases: *labgrid.resource.common.ManagedResource*

manager_cls

alias of *RemotePlaceManager*

__attrs_post_init__ ()

__attrs_attrs__ = (**Attribute**(name='target', default=NOTHING, validator=None, repr=True

__init__ (*target, name*) → None

Method generated by attrs for class RemotePlace.

__module__ = 'labgrid.resource.remote'

__repr__ ()

Method generated by attrs for class RemotePlace.

class labgrid.resource.remote.RemoteUSBResource (*target, name, host, busnum, devnum,*
path, vendor_id, model_id)

Bases: *labgrid.resource.common.NetworkResource*, *labgrid.resource.common.ManagedResource*

manager_cls

alias of *RemotePlaceManager*

```
__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True)
__init__(target, name, host, busnum, devnum, path, vendor_id, model_id) → None
    Method generated by attrs for class RemoteUSBResource.
__module__ = 'labgrid.resource.remote'
__repr__()
    Method generated by attrs for class RemoteUSBResource.
class labgrid.resource.remote.NetworkAndroidFastboot(target, name, host, busnum,
                                                    devnum, path, vendor_id,
                                                    model_id)
    Bases: labgrid.resource.remote.RemoteUSBResource
    __attrs_post_init__()
    __attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True)
__init__(target, name, host, busnum, devnum, path, vendor_id, model_id) → None
    Method generated by attrs for class NetworkAndroidFastboot.
__module__ = 'labgrid.resource.remote'
__repr__()
    Method generated by attrs for class NetworkAndroidFastboot.
class labgrid.resource.remote.NetworkIMXUSBLoader(target, name, host, busnum, devnum,
                                                    path, vendor_id, model_id)
    Bases: labgrid.resource.remote.RemoteUSBResource
    __attrs_post_init__()
    __attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True)
__init__(target, name, host, busnum, devnum, path, vendor_id, model_id) → None
    Method generated by attrs for class NetworkIMXUSBLoader.
__module__ = 'labgrid.resource.remote'
__repr__()
    Method generated by attrs for class NetworkIMXUSBLoader.
class labgrid.resource.remote.NetworkMXSUSBLoader(target, name, host, busnum, devnum,
                                                    path, vendor_id, model_id)
    Bases: labgrid.resource.remote.RemoteUSBResource
    __attrs_post_init__()
    __attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True)
__init__(target, name, host, busnum, devnum, path, vendor_id, model_id) → None
    Method generated by attrs for class NetworkMXSUSBLoader.
__module__ = 'labgrid.resource.remote'
__repr__()
    Method generated by attrs for class NetworkMXSUSBLoader.
class labgrid.resource.remote.NetworkRKUSBLoader(target, name, host, busnum, devnum,
                                                    path, vendor_id, model_id)
    Bases: labgrid.resource.remote.RemoteUSBResource
    __attrs_post_init__()
    __attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True)
```



```

__init__(target, name, host, busnum, devnum, path, vendor_id, model_id) → None
    Method generated by attrs for class NetworkRKUSBLoader.

__module__ = 'labgrid.resource.remote'

__repr__()
    Method generated by attrs for class NetworkRKUSBLoader.

class labgrid.resource.remote.NetworkAlteraUSBBlaster(target, name, host, busnum,
                                                    devnum, path, vendor_id,
                                                    model_id)

    Bases: labgrid.resource.remote.RemoteUSBResource

    __attrs_post_init__()

    __attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True
    __init__(target, name, host, busnum, devnum, path, vendor_id, model_id) → None
        Method generated by attrs for class NetworkAlteraUSBBlaster.

    __module__ = 'labgrid.resource.remote'

    __repr__()
        Method generated by attrs for class NetworkAlteraUSBBlaster.

class labgrid.resource.remote.NetworkSigrokUSBDevice(target, name, host, busnum,
                                                    devnum, path, vendor_id,
                                                    model_id, driver=None, chan-
                                                    nels=None)

    Bases: labgrid.resource.remote.RemoteUSBResource

    The NetworkSigrokUSBDevice describes a remotely accessible sigrok USB device

    __attrs_post_init__()

    __attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True
    __init__(target, name, host, busnum, devnum, path, vendor_id, model_id, driver=None, chan-
        nels=None) → None
        Method generated by attrs for class NetworkSigrokUSBDevice.

    __module__ = 'labgrid.resource.remote'

    __repr__()
        Method generated by attrs for class NetworkSigrokUSBDevice.

class labgrid.resource.remote.NetworkSigrokUSBSerialDevice(target, name,
                                                            host, busnum, de-
                                                            vnum, path, ven-
                                                            dor_id, model_id,
                                                            driver=None, chan-
                                                            nels=None)

    Bases: labgrid.resource.remote.RemoteUSBResource

    The NetworkSigrokUSBSerialDevice describes a remotely accessible sigrok USB device

    __attrs_post_init__()

    __attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True
    __init__(target, name, host, busnum, devnum, path, vendor_id, model_id, driver=None, chan-
        nels=None) → None
        Method generated by attrs for class NetworkSigrokUSBSerialDevice.

    __module__ = 'labgrid.resource.remote'

```

```
__repr__()  
    Method generated by attrs for class NetworkSigrokUSBSerialDevice.
```

```
class labgrid.resource.remote.NetworkUSBMassStorage(target, name, host, busnum,  
                                                    devnum, path, vendor_id,  
                                                    model_id)
```

Bases: *labgrid.resource.remote.RemoteUSBResource*

The NetworkUSBMassStorage describes a remotely accessible USB storage device

```
__attrs_post_init__()
```

```
__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True
```

```
__init__(target, name, host, busnum, devnum, path, vendor_id, model_id) → None  
    Method generated by attrs for class NetworkUSBMassStorage.
```

```
__module__ = 'labgrid.resource.remote'
```

```
__repr__()  
    Method generated by attrs for class NetworkUSBMassStorage.
```

```
class labgrid.resource.remote.NetworkUSBSDMuxDevice(target, name, host, busnum,  
                                                    devnum, path, vendor_id,  
                                                    model_id, control_path=None)
```

Bases: *labgrid.resource.remote.RemoteUSBResource*

The NetworkUSBSDMuxDevice describes a remotely accessible USBSDMux device

```
__attrs_post_init__()
```

```
__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True
```

```
__init__(target, name, host, busnum, devnum, path, vendor_id, model_id, control_path=None) →  
    None  
    Method generated by attrs for class NetworkUSBSDMuxDevice.
```

```
__module__ = 'labgrid.resource.remote'
```

```
__repr__()  
    Method generated by attrs for class NetworkUSBSDMuxDevice.
```

```
class labgrid.resource.remote.NetworkUSBSDWireDevice(target, name, host, bus-  
                                                    num, devnum, path, ven-  
                                                    dor_id, model_id, con-  
                                                    trol_serial=None)
```

Bases: *labgrid.resource.remote.RemoteUSBResource*

The NetworkUSBSDWireDevice describes a remotely accessible USBSDWire device

```
__attrs_post_init__()
```

```
__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True
```

```
__init__(target, name, host, busnum, devnum, path, vendor_id, model_id, control_serial=None) →  
    None  
    Method generated by attrs for class NetworkUSBSDWireDevice.
```

```
__module__ = 'labgrid.resource.remote'
```

```
__repr__()  
    Method generated by attrs for class NetworkUSBSDWireDevice.
```

```
class labgrid.resource.remote.NetworkSiSPMPowerPort(target, name, host, busnum,  
                                                    devnum, path, vendor_id,  
                                                    model_id, index=None)
```

Bases: *labgrid.resource.remote.RemoteUSBResource*

The NetworkSiSPMPowerPort describes a remotely accessible SiS-PM power port

```
__attrs_post_init__()
```

```
__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True
```

```
__init__(target, name, host, busnum, devnum, path, vendor_id, model_id, index=None) → None
```

Method generated by attrs for class NetworkSiSPMPowerPort.

```
__module__ = 'labgrid.resource.remote'
```

```
__repr__()
```

Method generated by attrs for class NetworkSiSPMPowerPort.

```
class labgrid.resource.remote.NetworkUSBPowerPort(target, name, host, busnum, de-
                                                    vnum, path, vendor_id, model_id,
                                                    index=None)
```

Bases: `labgrid.resource.remote.RemoteUSBResource`

The NetworkUSBPowerPort describes a remotely accessible USB hub port with power switching

```
__attrs_post_init__()
```

```
__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True
```

```
__init__(target, name, host, busnum, devnum, path, vendor_id, model_id, index=None) → None
```

Method generated by attrs for class NetworkUSBPowerPort.

```
__module__ = 'labgrid.resource.remote'
```

```
__repr__()
```

Method generated by attrs for class NetworkUSBPowerPort.

```
class labgrid.resource.remote.NetworkUSBVideo(target, name, host, busnum, devnum, path,
                                                vendor_id, model_id)
```

Bases: `labgrid.resource.remote.RemoteUSBResource`

The NetworkUSBVideo describes a remotely accessible USB video device

```
__attrs_post_init__()
```

```
__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True
```

```
__init__(target, name, host, busnum, devnum, path, vendor_id, model_id) → None
```

Method generated by attrs for class NetworkUSBVideo.

```
__module__ = 'labgrid.resource.remote'
```

```
__repr__()
```

Method generated by attrs for class NetworkUSBVideo.

```
class labgrid.resource.remote.NetworkUSBTMC(target, name, host, busnum, devnum, path,
                                              vendor_id, model_id)
```

Bases: `labgrid.resource.remote.RemoteUSBResource`

The NetworkUSBTMC describes a remotely accessible USB TMC device

```
__attrs_post_init__()
```

```
__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True
```

```
__init__(target, name, host, busnum, devnum, path, vendor_id, model_id) → None
```

Method generated by attrs for class NetworkUSBTMC.

```
__module__ = 'labgrid.resource.remote'
```

```
__repr__()
```

Method generated by attrs for class NetworkUSBTMC.

```
class labgrid.resource.remote.NetworkDeditecRelais8(target, name, host, busnum,
                                                    devnum, path, vendor_id,
                                                    model_id, index=None, in-
                                                    vert=False)
```

Bases: *labgrid.resource.remote.RemoteUSBResource*

The NetworkDeditecRelais8 describes a remotely accessible USB relais port

```
__attrs_post_init__()
```

```
__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True
```

```
__init__(target, name, host, busnum, devnum, path, vendor_id, model_id, index=None, invert=False)
              → None
```

Method generated by attrs for class NetworkDeditecRelais8.

```
__module__ = 'labgrid.resource.remote'
```

```
__repr__()
```

Method generated by attrs for class NetworkDeditecRelais8.

```
class labgrid.resource.remote.NetworkSysfsGPIO(target, name, host, index)
```

Bases: *labgrid.resource.common.NetworkResource*, *labgrid.resource.common.ManagedResource*

```
manager_cls
```

The NetworkSysfsGPIO describes a remotely accessible gpio line

alias of *RemotePlaceManager*

```
__attrs_post_init__()
```

```
__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True
```

```
__init__(target, name, host, index) → None
```

Method generated by attrs for class NetworkSysfsGPIO.

```
__module__ = 'labgrid.resource.remote'
```

```
__repr__()
```

Method generated by attrs for class NetworkSysfsGPIO.

```
class labgrid.resource.remote.NetworkLXAIOBusNode(target, name, host, node)
```

Bases: *labgrid.resource.common.ManagedResource*

```
manager_cls
```

alias of *RemotePlaceManager*

```
__attrs_post_init__()
```

```
__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True
```

```
__init__(target, name, host, node) → None
```

Method generated by attrs for class NetworkLXAIOBusNode.

```
__module__ = 'labgrid.resource.remote'
```

```
__repr__()
```

Method generated by attrs for class NetworkLXAIOBusNode.

```
class labgrid.resource.remote.NetworkLXAIOBusPIO(target, name, host, node, pin, in-
                                                    vert=False)
```

Bases: *labgrid.resource.remote.NetworkLXAIOBusNode*

```
__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True
```

```
__init__(target, name, host, node, pin, invert=False) → None
    Method generated by attrs for class NetworkLXAIOBusPIO.

__module__ = 'labgrid.resource.remote'

__repr__()
    Method generated by attrs for class NetworkLXAIOBusPIO.
```

labgrid.resource.serialport module

```
class labgrid.resource.serialport.RawSerialPort(target, name, port=None,
                                                speed=115200)
```

Bases: `labgrid.resource.base.SerialPort`, `labgrid.resource.common.Resource`

RawSerialPort describes a serialport which is available on the local computer.

```
__attrs_post_init__()

__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True)

__init__(target, name, port=None, speed=115200) → None
    Method generated by attrs for class RawSerialPort.

__module__ = 'labgrid.resource.serialport'

__repr__()
    Method generated by attrs for class RawSerialPort.
```

```
class labgrid.resource.serialport.NetworkSerialPort(target, name, host, port,
                                                    speed=115200,
                                                    protocol='rfc2217')
```

Bases: `labgrid.resource.common.NetworkResource`

A NetworkSerialPort is a remotely accessible serialport, usually accessed via rfc2217 or tcp raw.

Parameters

- **port** (*str*) – socket port to connect to
- **speed** (*int*) – speed of the port e.g. 9800
- **protocol** (*str*) – connection protocol: “raw” or “rfc2217”

```
__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True)

__init__(target, name, host, port, speed=115200, protocol='rfc2217') → None
    Method generated by attrs for class NetworkSerialPort.

__module__ = 'labgrid.resource.serialport'

__repr__()
    Method generated by attrs for class NetworkSerialPort.
```

labgrid.resource.sigrok module

```
class labgrid.resource.sigrok.SigrokDevice(target, name, driver='demo',
                                           channels=None)
```

Bases: `labgrid.resource.common.Resource`

The SigrokDevice describes an attached sigrok device with driver and channel mapping

Parameters

- **driver** (*str*) – driver to use with sigrok
- **channels** (*str*) – a sigrok channel mapping as described in the sigrok-cli man page

```
__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True)
__init__ (target, name, driver='demo', channels=None) → None
    Method generated by attrs for class SigrokDevice.
__module__ = 'labgrid.resource.sigrok'
__repr__ ()
    Method generated by attrs for class SigrokDevice.
```

labgrid.resource.suggest module

```
class labgrid.resource.suggest.Suggester (args)
    Bases: object
    __init__ (args)
        Initialize self. See help(type(self)) for accurate signature.
    suggest_callback (resource, meta, suggestions)
    run ()
    __dict__ = mappingproxy({'__module__': 'labgrid.resource.suggest', '__init__': <func
    __module__ = 'labgrid.resource.suggest'
    __weakref__
        list of weak references to the object (if defined)
labgrid.resource.suggest.main ()
```

labgrid.resource.udev module

```
class labgrid.resource.udev.UdevManager
    Bases: labgrid.resource.common.ResourceManager
    __attrs_post_init__ ()
    on_resource_added (resource)
    poll ()
    __attrs_attrs__ = ()
    __init__ () → None
        Method generated by attrs for class UdevManager.
    __module__ = 'labgrid.resource.udev'
    __repr__ ()
        Method generated by attrs for class UdevManager.
class labgrid.resource.udev.USBResource (target, name, match=NOTHING, device=None,
                                         suggest=False)
    Bases: labgrid.resource.common.ManagedResource
    manager_cls
        alias of UdevManager
```

```

__attrs_post_init__()
filter_match(device)
suggest_match(device)
try_match(device)
update()

property busnum
property devnum
property path
property vendor_id
property model_id

read_attr(attribute)
    read uncached attribute value from sysfs

    pyudev currently supports only cached access to attributes, so we read directly from sysfs.

__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True

__init__(target, name, match=NOTHING, device=None, suggest=False) → None
    Method generated by attrs for class USBResource.

__module__ = 'labgrid.resource.udev'

__repr__()
    Method generated by attrs for class USBResource.

class labgrid.resource.udev.USBSerialPort(target, name, match=NOTHING, device=None,
                                           suggest=False, port=None, speed=115200)
    Bases: labgrid.resource.udev.USBResource, labgrid.resource.base.SerialPort
    __attrs_post_init__()
    update()
    __attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True
    __init__(target, name, match=NOTHING, device=None, suggest=False, port=None, speed=115200)
        → None
        Method generated by attrs for class USBSerialPort.
    __module__ = 'labgrid.resource.udev'
    __repr__()
        Method generated by attrs for class USBSerialPort.

class labgrid.resource.udev.USBMassStorage(target, name, match=NOTHING, de-
                                           vice=None, suggest=False)
    Bases: labgrid.resource.udev.USBResource
    __attrs_post_init__()
    property avail
    property path
    __attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True
    __init__(target, name, match=NOTHING, device=None, suggest=False) → None
        Method generated by attrs for class USBMassStorage.

```

```
__module__ = 'labgrid.resource.udev'

__repr__ ()
    Method generated by attrs for class USBMassStorage.

class labgrid.resource.udev.IMXUSBLoader (target, name, match=NOTHING, device=None,
                                          suggest=False)
    Bases: labgrid.resource.udev.USBResource
    filter_match (device)

    __attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True
    __init__ (target, name, match=NOTHING, device=None, suggest=False) → None
        Method generated by attrs for class IMXUSBLoader.

    __module__ = 'labgrid.resource.udev'

    __repr__ ()
        Method generated by attrs for class IMXUSBLoader.

class labgrid.resource.udev.RKUSBLoader (target, name, match=NOTHING, device=None,
                                          suggest=False)
    Bases: labgrid.resource.udev.USBResource
    filter_match (device)

    __attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True
    __init__ (target, name, match=NOTHING, device=None, suggest=False) → None
        Method generated by attrs for class RKUSBLoader.

    __module__ = 'labgrid.resource.udev'

    __repr__ ()
        Method generated by attrs for class RKUSBLoader.

class labgrid.resource.udev.MXSUSBLoader (target, name, match=NOTHING, device=None,
                                          suggest=False)
    Bases: labgrid.resource.udev.USBResource
    filter_match (device)

    __attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True
    __init__ (target, name, match=NOTHING, device=None, suggest=False) → None
        Method generated by attrs for class MXSUSBLoader.

    __module__ = 'labgrid.resource.udev'

    __repr__ ()
        Method generated by attrs for class MXSUSBLoader.

class labgrid.resource.udev.AndroidFastboot (target, name, match=NOTHING,
                                              device=None, suggest=False,
                                              usb_vendor_id='1d6b',
                                              usb_product_id='0104')
    Bases: labgrid.resource.udev.USBResource
    filter_match (device)

    __attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True
    __init__ (target, name, match=NOTHING, device=None, suggest=False, usb_vendor_id='1d6b',
        usb_product_id='0104') → None
        Method generated by attrs for class AndroidFastboot.
```



```

__module__ = 'labgrid.resource.udev'

__repr__ ()
    Method generated by attrs for class AndroidFastboot.

class labgrid.resource.udev.USBEthernetInterface (target, name, match=NOTHING,
                                                    device=None, suggest=False, if-
                                                    name=None)

Bases: labgrid.resource.udev.USBResource, labgrid.resource.base.
EthernetInterface

__attrs_post_init__ ()

update ()

property if_state

__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True
__init__ (target, name, match=NOTHING, device=None, suggest=False, ifname=None) → None
    Method generated by attrs for class USBEthernetInterface.

__module__ = 'labgrid.resource.udev'

__repr__ ()
    Method generated by attrs for class USBEthernetInterface.

class labgrid.resource.udev.AlteraUSBBlaster (target, name, match=NOTHING, de-
                                              vice=None, suggest=False)

Bases: labgrid.resource.udev.USBResource

filter_match (device)

__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True
__init__ (target, name, match=NOTHING, device=None, suggest=False) → None
    Method generated by attrs for class AlteraUSBBlaster.

__module__ = 'labgrid.resource.udev'

__repr__ ()
    Method generated by attrs for class AlteraUSBBlaster.

class labgrid.resource.udev.SigrokUSBDevice (target, name, match=NOTHING, de-
                                              vice=None, suggest=False, driver=None,
                                              channels=None)

Bases: labgrid.resource.udev.USBResource

```

The SigrokUSBDevice describes an attached sigrok device with driver and optional channel mapping, it is identified via usb using udev.

This is used for devices which communicate over a custom USB protocol.

Parameters

- **driver** (*str*) – driver to use with sigrok
- **channels** (*str*) – a sigrok channel mapping as described in the sigrok-cli man page

```

__attrs_post_init__ ()

__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True
__init__ (target, name, match=NOTHING, device=None, suggest=False, driver=None, chan-
        nels=None) → None
    Method generated by attrs for class SigrokUSBDevice.

```

```
__module__ = 'labgrid.resource.udev'
```

```
__repr__()
```

Method generated by attrs for class SigrokUSBDevice.

```
class labgrid.resource.udev.SigrokUSBSerialDevice(target, name, match=NOTHING,
                                                    device=None, suggest=False,
                                                    driver=None, channels=None)
```

Bases: `labgrid.resource.udev.USBResource`

The SigrokUSBSerialDevice describes an attached sigrok device with driver and optional channel mapping, it is identified via usb using udev.

This is used for devices which communicate over an emulated serial device.

Parameters

- **driver** (*str*) – driver to use with sigrok
- **channels** (*str*) – a sigrok channel mapping as described in the sigrok-cli man page

```
__attrs_post_init__()
```

property path

```
__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True
```

```
__init__(target, name, match=NOTHING, device=None, suggest=False, driver=None, chan-
            nels=None) → None
```

Method generated by attrs for class SigrokUSBSerialDevice.

```
__module__ = 'labgrid.resource.udev'
```

```
__repr__()
```

Method generated by attrs for class SigrokUSBSerialDevice.

```
class labgrid.resource.udev.USBSDWireDevice(target, name, match=NOTHING,
                                              device=None, suggest=False, con-
                                              trol_path=None, disk_path=None)
```

Bases: `labgrid.resource.udev.USBResource`

The USBSDWireDevice describes an attached SDWire device, it is identified via USB using udev

```
__attrs_post_init__()
```

property avail

poll()

property path

```
__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True
```

```
__init__(target, name, match=NOTHING, device=None, suggest=False, control_path=None,
            disk_path=None) → None
```

Method generated by attrs for class USBSDWireDevice.

```
__module__ = 'labgrid.resource.udev'
```

```
__repr__()
```

Method generated by attrs for class USBSDWireDevice.

```
class labgrid.resource.udev.USBSDMuxDevice(target, name, match=NOTHING,
                                             device=None, suggest=False, con-
                                             trol_path=None, disk_path=None)
```

Bases: `labgrid.resource.udev.USBResource`

The USBSDMuxDevice describes an attached USBSDMux device, it is identified via USB using udev

```
__attrs_post_init__()
```

```
property avail
```

```
poll()
```

```
property path
```

```
__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True
```

```
__init__(target, name, match=NOTHING, device=None, suggest=False, control_path=None,
          disk_path=None) → None
```

Method generated by attrs for class USBSDMuxDevice.

```
__module__ = 'labgrid.resource.udev'
```

```
__repr__()
```

Method generated by attrs for class USBSDMuxDevice.

```
class labgrid.resource.udev.USBPowerPort(target, name, match=NOTHING, device=None,
                                          suggest=False, index=None)
```

Bases: *labgrid.resource.udev.USBResource*

The USBPowerPort describes a single port on an USB hub which supports power control.

Parameters *index* (*int*) – index of the downstream port on the USB hub

```
__attrs_post_init__()
```

```
__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True
```

```
__init__(target, name, match=NOTHING, device=None, suggest=False, index=None) → None
```

Method generated by attrs for class USBPowerPort.

```
__module__ = 'labgrid.resource.udev'
```

```
__repr__()
```

Method generated by attrs for class USBPowerPort.

```
class labgrid.resource.udev.SiSPMPowerPort(target, name, match=NOTHING, de-
                                           vice=None, suggest=False, index=0)
```

Bases: *labgrid.resource.udev.USBResource*

This resource describes a SiS-PM (Silver Shield PM) power port.

Parameters *index* (*int*) – port index

```
filter_match(device)
```

```
__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True
```

```
__init__(target, name, match=NOTHING, device=None, suggest=False, index=0) → None
```

Method generated by attrs for class SiSPMPowerPort.

```
__module__ = 'labgrid.resource.udev'
```

```
__repr__()
```

Method generated by attrs for class SiSPMPowerPort.

```
class labgrid.resource.udev.USBVideo(target, name, match=NOTHING, device=None, sug-
                                     gest=False)
```

Bases: *labgrid.resource.udev.USBResource*

```
__attrs_post_init__()
```

```
property path
```

```
__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True
__init__(target, name, match=NOTHING, device=None, suggest=False) → None
    Method generated by attrs for class USBVideo.
__module__ = 'labgrid.resource.udev'
__repr__()
    Method generated by attrs for class USBVideo.
class labgrid.resource.udev.USBTMC(target, name, match=NOTHING, device=None, sug-
                                gest=False)
    Bases: labgrid.resource.udev.USBResource
    __attrs_post_init__()
    property path
__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True
__init__(target, name, match=NOTHING, device=None, suggest=False) → None
    Method generated by attrs for class USBTMC.
__module__ = 'labgrid.resource.udev'
__repr__()
    Method generated by attrs for class USBTMC.
class labgrid.resource.udev.DeditecRelais8(target, name, match=NOTHING, de-
                                vice=None, suggest=False, index=None,
                                invert=False)
    Bases: labgrid.resource.udev.USBResource
__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True
__init__(target, name, match=NOTHING, device=None, suggest=False, index=None, invert=False)
    → None
    Method generated by attrs for class DeditecRelais8.
__module__ = 'labgrid.resource.udev'
__repr__()
    Method generated by attrs for class DeditecRelais8.
__attrs_post_init__()
    property path
```

labgrid.resource.xenamanager module

```
class labgrid.resource.xenamanager.XenaManager(target, name, hostname)
    Bases: labgrid.resource.common.Resource
    Hostname/IP identifying the manageent address of the xena tester
__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True
__init__(target, name, hostname) → None
    Method generated by attrs for class XenaManager.
__module__ = 'labgrid.resource.xenamanager'
__repr__()
    Method generated by attrs for class XenaManager.
```

labgrid.resource.ykushpowerport module

class labgrid.resource.ykushpowerport.YKUSHPowerPort (*target, name, serial, index*)

Bases: *labgrid.resource.common.Resource*

This resource describes a YEPKIT YKUSH switchable USB hub.

Parameters

- **serial** (*str*) – serial of the YKUSH device
- **index** (*int*) – port index

__attrs_attrs__ = (**Attribute**(name='target', default=NOTHING, validator=None, repr=True

__init__ (*target, name, serial, index*) → None
Method generated by attrs for class YKUSHPowerPort.

__module__ = 'labgrid.resource.ykushpowerport'

__repr__ ()
Method generated by attrs for class YKUSHPowerPort.

labgrid.strategy package

Submodules

labgrid.strategy.bareboxstrategy module

class labgrid.strategy.bareboxstrategy.Status

Bases: *enum.Enum*

An enumeration.

unknown = 0

off = 1

barebox = 2

shell = 3

__module__ = 'labgrid.strategy.bareboxstrategy'

class labgrid.strategy.bareboxstrategy.BareboxStrategy (*target, name, status=<Status.unknown: 0>*)

Bases: *labgrid.strategy.common.Strategy*

BareboxStrategy - Strategy to switch to barebox or shell

bindings = {'barebox': <class 'labgrid.driver.bareboxdriver.BareboxDriver'>, 'power':

__attrs_post_init__ ()

transition (*status, *, step*)

__attrs_attrs__ = (**Attribute**(name='target', default=NOTHING, validator=None, repr=True

__init__ (*target, name, status=<Status.unknown: 0>*) → None
Method generated by attrs for class BareboxStrategy.

__module__ = 'labgrid.strategy.bareboxstrategy'

`__repr__()`
Method generated by attrs for class BareboxStrategy.

labgrid.strategy.common module

exception `labgrid.strategy.common.StrategyError(msg)`
Bases: `Exception`

`__attrs_attrs__` = `(Attribute(name='msg', default=NOTHING, validator=<instance_of valid`

`__init__(msg)` → `None`
Method generated by attrs for class StrategyError.

`__module__` = `'labgrid.strategy.common'`

`__repr__()`
Method generated by attrs for class StrategyError.

`__weakref__`
list of weak references to the object (if defined)

class `labgrid.strategy.common.Strategy(target, name)`
Bases: `labgrid.driver.common.Driver`

Represents a strategy which places a target into a requested state by calling specific drivers. A strategy usually needs to know some details of a given target.

Life cycle: - create - bind (n times) - usage

TODO: This might also be just a driver?

`__attrs_post_init__()`

`on_client_bound(client)`
Called by the Target after a new client has been bound

`on_activate()`
Called by the Target when this object has been activated

`on_deactivate()`
Called by the Target when this object has been deactivated

`resolve_conflicts(client)`
Called by the Target to allow this object to deactivate conflicting clients.

`transition(status)`

`force(status)`

`__attrs_attrs__` = `(Attribute(name='target', default=NOTHING, validator=None, repr=True`

`__init__(target, name)` → `None`
Method generated by attrs for class Strategy.

`__module__` = `'labgrid.strategy.common'`

`__repr__()`
Method generated by attrs for class Strategy.

labgrid.strategy.dockerstrategy module

class labgrid.strategy.dockerstrategy.**Status**

Bases: `enum.Enum`

The possible states of a docker container

unknown = 0

gone = 1

accessible = 2

__module__ = 'labgrid.strategy.dockerstrategy'

class labgrid.strategy.dockerstrategy.**DockerStrategy** (*target, name, status=<Status.unknown: 0>*)

Bases: `labgrid.strategy.common.Strategy`

DockerStrategy enables the user to directly transition to a state where a fresh docker container has been created and is ready for access (e.g. shell access via SSH if the docker image runs an SSH daemon).

bindings = {'docker_driver': <class 'labgrid.driver.dockerdriver.DockerDriver'>}

__attrs_post_init__ ()

transition (*status*)

__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True

__init__ (*target, name, status=<Status.unknown: 0>*) → None

Method generated by attrs for class DockerStrategy.

__module__ = 'labgrid.strategy.dockerstrategy'

__repr__ ()

Method generated by attrs for class DockerStrategy.

labgrid.strategy.graphstrategy module

exception labgrid.strategy.graphstrategy.**GraphStrategyError** (*msg*)

Bases: `labgrid.strategy.common.StrategyError`

Generic GraphStrategy error

__module__ = 'labgrid.strategy.graphstrategy'

exception labgrid.strategy.graphstrategy.**InvalidGraphStrategyError** (*msg*)

Bases: `labgrid.strategy.graphstrategy.GraphStrategyError`

GraphStrategy error raised during initialization of broken strategies

__module__ = 'labgrid.strategy.graphstrategy'

exception labgrid.strategy.graphstrategy.**GraphStrategyRuntimeError** (*msg*)

Bases: `labgrid.strategy.graphstrategy.GraphStrategyError`

GraphStrategy error raised during runtime when used in unintended ways

__module__ = 'labgrid.strategy.graphstrategy'

class labgrid.strategy.graphstrategy.**GraphStrategy** (*target, name*)

Bases: `labgrid.strategy.common.Strategy`

__attrs_post_init__ ()

invalidate()

Marks the path to the current state as out-of-date. Subsequent transition() calls will start from the root state. Will be called if exceptions in state methods occur.

transition (*state*, *via=None*)

Computes the path from root state (via “via” state, if given) to given state. If the computed path is fully incremental to the path executed previously, only the state’s methods relative to the previous path are executed. Otherwise all states’ methods of the computed path (starting from the root node) are executed.

find_abs_path (*state*, *via=None*)

Computes the absolute path from the root state, via “via” (if given), to the given state.

find_rel_path (*path*)

If the given path is fully incremental to the path executed before, returns the path relative to the previously executed one. Otherwise the given path is returned.

property graph

Returns a graphviz.Digraph for the directed graph the inheriting strategy represents.

The graph can be rendered with: `mystrategy.graph.render("filename")` # renders to filename.png

classmethod depends (**dependencies*)

@depends decorator used to list states the decorated state directly depends on.

__module__ = 'labgrid.strategy.graphstrategy'

labgrid.strategy.shellstrategy module

class labgrid.strategy.shellstrategy.Status

Bases: enum.Enum

An enumeration.

unknown = 0

off = 1

shell = 2

__module__ = 'labgrid.strategy.shellstrategy'

class labgrid.strategy.shellstrategy.ShellStrategy (*target*, *name*, *status=<Status.unknown: 0>*)

Bases: labgrid.strategy.common.Strategy

ShellStrategy - Strategy to switch to shell

bindings = {'power': <class 'labgrid.protocol.powerprotocol.PowerProtocol'>, 'shell':

__attrs_post_init__ ()

transition (*status*, ***, *step*)

force (*status*, ***, *step*)

__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True

__init__ (*target*, *name*, *status=<Status.unknown: 0>*) → None

Method generated by attrs for class ShellStrategy.

__module__ = 'labgrid.strategy.shellstrategy'

`__repr__()`
Method generated by attrs for class ShellStrategy.

labgrid.strategy.ubootstrategy module

class labgrid.strategy.ubootstrategy.**Status**

Bases: `enum.Enum`

An enumeration.

`unknown = 0`

`off = 1`

`uboot = 2`

`shell = 3`

`__module__ = 'labgrid.strategy.ubootstrategy'`

class labgrid.strategy.ubootstrategy.**UBootStrategy**(*target*, *name*, *status=<Status.unknown: 0>*)

Bases: `labgrid.strategy.common.Strategy`

UbootStrategy - Strategy to switch to uboot or shell

`bindings = {'power': <class 'labgrid.protocol.powerprotocol.PowerProtocol'>, 'shell':`

`__attrs_post_init__()`

`transition(status)`

`__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True`

`__init__(target, name, status=<Status.unknown: 0>) → None`

Method generated by attrs for class UBootStrategy.

`__module__ = 'labgrid.strategy.ubootstrategy'`

`__repr__()`

Method generated by attrs for class UBootStrategy.

labgrid.util package

Subpackages

labgrid.util.agents package

Submodules

labgrid.util.agents.deditec_relais8 module

labgrid.util.agents.dummy module

labgrid.util.agents.dummy.**handle_neg**(*value*)

labgrid.util.agents.sysfsgpio module

This module implements switching GPIOs via sysfs GPIO kernel interface.

Takes an integer property ‘index’ which refers to the already exported GPIO device.

class labgrid.util.agents.sysfsgpio.GpioDigitalOutput (*index*)

Bases: object

__init__ (*index*)

Initialize self. See help(type(self)) for accurate signature.

__del__ ()

get ()

set (*status*)

__dict__ = mappingproxy({'__module__': 'labgrid.util.agents.sysfsgpio', '__gpio_sysfs_

__module__ = 'labgrid.util.agents.sysfsgpio'

__weakref__

list of weak references to the object (if defined)

labgrid.util.agents.sysfsgpio.**handle_set** (*index*, *status*)

labgrid.util.agents.sysfsgpio.**handle_get** (*index*)

Submodules

labgrid.util.agent module

labgrid.util.agent.**b2s** (*b*)

labgrid.util.agent.**s2b** (*s*)

class labgrid.util.agent.Agent

Bases: object

__init__ ()

Initialize self. See help(type(self)) for accurate signature.

send (*data*)

register (*name*, *func*)

load (*name*, *source*)

list ()

run ()

__dict__ = mappingproxy({'__module__': 'labgrid.util.agent', '__init__': <function A

__module__ = 'labgrid.util.agent'

__weakref__

list of weak references to the object (if defined)

labgrid.util.agent.**handle_test** (**args*, ***kwargs*)

labgrid.util.agent.**handle_error** (*message*)

labgrid.util.agent.**handle_usbttmc** (*index*, *cmd*, *read=False*)

```
labgrid.util.agent.main()
```

labgrid.util.agentwrapper module

```
labgrid.util.agentwrapper.b2s(b)
```

```
labgrid.util.agentwrapper.s2b(s)
```

```
exception labgrid.util.agentwrapper.AgentError
    Bases: Exception
```

```
    __module__ = 'labgrid.util.agentwrapper'
```

```
    __weakref__
```

```
        list of weak references to the object (if defined)
```

```
exception labgrid.util.agentwrapper.AgentException
    Bases: Exception
```

```
    __module__ = 'labgrid.util.agentwrapper'
```

```
    __weakref__
```

```
        list of weak references to the object (if defined)
```

```
class labgrid.util.agentwrapper.MethodProxy(wrapper, name)
    Bases: object
```

```
    __init__(wrapper, name)
```

```
        Initialize self. See help(type(self)) for accurate signature.
```

```
    __call__(*args, **kwargs)
```

```
        Call self as a function.
```

```
    __dict__ = mappingproxy({'__module__': 'labgrid.util.agentwrapper', '__init__': <fun
```

```
    __module__ = 'labgrid.util.agentwrapper'
```

```
    __weakref__
```

```
        list of weak references to the object (if defined)
```

```
class labgrid.util.agentwrapper.ModuleProxy(wrapper, name)
    Bases: object
```

```
    __init__(wrapper, name)
```

```
        Initialize self. See help(type(self)) for accurate signature.
```

```
    __getattr__(name)
```

```
    __dict__ = mappingproxy({'__module__': 'labgrid.util.agentwrapper', '__init__': <fun
```

```
    __module__ = 'labgrid.util.agentwrapper'
```

```
    __weakref__
```

```
        list of weak references to the object (if defined)
```

```
class labgrid.util.agentwrapper.AgentWrapper(host=None)
    Bases: object
```

```
    __init__(host=None)
```

```
        Initialize self. See help(type(self)) for accurate signature.
```

```
    __del__()
```

```
    __getattr__(name)
```

```
call (method, *args, **kwargs)  
__dict__ = mappingproxy({'__module__': 'labgrid.util.agentwrapper', '__init__': <fun  
__module__ = 'labgrid.util.agentwrapper'  
__weakref__  
    list of weak references to the object (if defined)  
load (name)  
close ()
```

labgrid.util.atomic module

```
labgrid.util.atomic.atomic_replace (filename, data)
```

labgrid.util.dict module

This module contains helper functions for working with dictionaries.

```
labgrid.util.dict.diff_dict (old, new)  
    Compares old and new dictionaries, yielding for each difference (key, old_value, new_value). None is used for  
    missing values.  
labgrid.util.dict.flat_dict (d)  
labgrid.util.dict.filter_dict (d, cls, warn=False)  
    Returns a copy a dictionary which only contains the attributes defined on an attrs class.  
labgrid.util.dict.find_dict (d, key)  
    Recursively search for a key in a dictionary
```

Parameters

- **d** (*dict*) – The dictionary to recursively search through
- **key** (*str*) – The key to search for

labgrid.util.exceptions module

```
exception labgrid.util.exceptions.NoValidDriverError (msg)  
    Bases: Exception  
__attrs_attrs__ = (Attribute (name='msg', default=NOTHING, validator=<instance_of valid  
__init__ (msg) → None  
    Method generated by attrs for class NoValidDriverError.  
__module__ = 'labgrid.util.exceptions'  
__repr__ ()  
    Method generated by attrs for class NoValidDriverError.  
__weakref__  
    list of weak references to the object (if defined)
```

labgrid.util.expect module

```
class labgrid.util.expect.PtxExpect (driver)
    Bases: pexpect.pty_spawn.spawn

    labgrid Wrapper of the pexpect module.

    This class provides pexpect functionality for the ConsoleProtocol classes. driver: ConsoleProtocol object to be
    passed in

    __init__ (driver)
        Initializes a pexpect spawn instance with required configuration

    send (s)
        Write to underlying transport, return number of bytes written

    read_nonblocking (size=1, timeout=-1)
        Pexpects needs a nonblocking read function, simply use pyserial with a timeout of 0.

    __module__ = 'labgrid.util.expect'
```

labgrid.util.helper module

```
labgrid.util.helper.get_free_port ()
    Helper function to always return an unused port.

labgrid.util.helper.get_user ()
    Get the username of the current user.

class labgrid.util.helper.ProcessWrapper (callbacks=NOTHING)
    Bases: object

    loglevel = 20

    check_output (command, *, print_on_silent_log=False)
        Run a command and supply the output to callback functions

    register (callback)
        Register a callback with the ProcessWrapper

    unregister (callback)
        Unregister a callback with the ProcessWrapper

    static log_callback (message, process)
        Logs process output message along with its pid.

    static print_callback (message, _)
        Prints process output message.

    enable_logging ()
        Enables process output to the logging interface.

    disable_logging ()
        Disables process output logging.

    enable_print ()
        Enables process output to print.

    disable_print ()
        Disables process output printing.

    __attrs_attrs__ = (Attribute(name='callbacks', default=Factory(factory=<class 'list'>,
```

```
__dict__ = mappingproxy({'__module__': 'labgrid.util.helper', 'loglevel': 20, 'check'
__eq__(other)
    Method generated by attrs for class ProcessWrapper.
__ge__(other)
    Method generated by attrs for class ProcessWrapper.
__gt__(other)
    Method generated by attrs for class ProcessWrapper.
__hash__ = None
__init__(callbacks=NOTHING) → None
    Method generated by attrs for class ProcessWrapper.
__le__(other)
    Method generated by attrs for class ProcessWrapper.
__lt__(other)
    Method generated by attrs for class ProcessWrapper.
__module__ = 'labgrid.util.helper'
__ne__(other)
    Method generated by attrs for class ProcessWrapper.
__repr__()
    Method generated by attrs for class ProcessWrapper.
__weakref__
    list of weak references to the object (if defined)
```

labgrid.util.managedfile module

```
class labgrid.util.managedfile.ManagedFile(local_path, resource, detect_nfs=True)
```

Bases: object

The ManagedFile allows the synchronisation of a file to a remote host. It has to be created with the to be synced file and the target resource as argument:

```
:: from labgrid.util.managedfile import ManagedFile
```

```
    ManagedFile("/tmp/examplefile", <your-resource>)
```

Synchronisation is done with the sync_to_resource method.

```
__attrs_post_init__()
```

```
sync_to_resource()
```

sync the file to the host specified in a resource

Raises `ExecutionError` – if the SSH connection/copy fails

```
get_remote_path()
```

Retrieve the remote file path

Returns path to the file on the remote host

Return type str

```
get_hash()
```

Retrieve the hash of the file

Returns SHA256 hexdigest of the file

Return type str

```
__attrs_attrs__ = (Attribute(name='local_path', default=NOTHING, validator=<instance_o
__dict__ = mappingproxy({'__module__': 'labgrid.util.managedfile', '__doc__': 'The
__eq__(other)
    Method generated by attrs for class ManagedFile.
__ge__(other)
    Method generated by attrs for class ManagedFile.
__gt__(other)
    Method generated by attrs for class ManagedFile.
__hash__ = None
__init__(local_path, resource, detect_nfs=True) → None
    Method generated by attrs for class ManagedFile.
__le__(other)
    Method generated by attrs for class ManagedFile.
__lt__(other)
    Method generated by attrs for class ManagedFile.
__module__ = 'labgrid.util.managedfile'
__ne__(other)
    Method generated by attrs for class ManagedFile.
__repr__()
    Method generated by attrs for class ManagedFile.
__weakref__
    list of weak references to the object (if defined)
```

labgrid.util.marker module

```
labgrid.util.marker.gen_marker()
```

labgrid.util.proxy module

labgrid.util.qmp module

```
class labgrid.util.qmp.QMPMonitor(monitor_out, monitor_in)
    Bases: object
    __attrs_post_init__()
    execute(command)
    __attrs_attrs__ = (Attribute(name='monitor_out', default=NOTHING, validator=None, repr
    __dict__ = mappingproxy({'__module__': 'labgrid.util.qmp', '__attrs_post_init__': <f
    __init__(monitor_out, monitor_in) → None
        Method generated by attrs for class QMPMonitor.
    __module__ = 'labgrid.util.qmp'
```

`__repr__()`
Method generated by attrs for class QMPMonitor.

`__weakref__`
list of weak references to the object (if defined)

exception `labgrid.util.qmp.QMPError(msg)`
Bases: `Exception`

`__attrs_attrs__` = `(Attribute(name='msg', default=NOTHING, validator=<instance of valid`

`__init__(msg) → None`
Method generated by attrs for class QMPError.

`__module__` = `'labgrid.util.qmp'`

`__repr__()`
Method generated by attrs for class QMPError.

`__weakref__`
list of weak references to the object (if defined)

labgrid.util.ssh module

class `labgrid.util.ssh.SSHConnection(host)`
Bases: `object`

SSHConnections are individual connections to hosts managed by a control socket. In addition to command execution this class also provides an interface to manage port forwardings. These are used in the remote infrastructure to tunnel multiple connections over one SSH link.

A public identity infrastructure is assumed, no extra username or passwords are supported.

`__attrs_post_init__()`

`get_prefix()`

run (*command*, *, *codec*='utf-8', *decodeerrors*='strict', *force_tty*=False, *stderr_merge*=False, *stderr_loglevel*=None, *stdout_loglevel*=None)
Run a command over the SSHConnection

Parameters

- **command** (*string*) – The command to run
- **codec** (*string*, *optional*) – output encoding. Defaults to “utf-8”.
- **decodeerrors** (*string*, *optional*) – behavior on decode errors. Defaults to “strict”. Refer to stdtypes’ bytes.decode for details.
- **force_tty** (*bool*, *optional*) – force allocate a tty (ssh -tt). Defaults to False
- **stderr_merge** (*bool*, *optional*) – merge ssh subprocess stderr into stdout. Defaults to False.
- **stdout_loglevel** (*int*, *optional*) – log stdout with specific log level as well. Defaults to None, i.e. don’t log.
- **stderr_loglevel** (*int*, *optional*) – log stderr with specific log level as well. Defaults to None, i.e. don’t log.

Returns (stdout, stderr, returncode)

run_check (*command*, *, *codec*='utf-8', *decodeerrors*='strict', *force_tty*=False, *stderr_merge*=False, *stderr_loglevel*=None, *stdout_loglevel*=None)

Runs a command over the SSHConnection returns the output if successful, raises ExecutionError otherwise.

Except for the means of returning the value, this is equivalent to run.

Parameters

- **command** (*string*) – The command to run
- **codec** (*string*, *optional*) – output encoding. Defaults to “utf-8”.
- **decodeerrors** (*string*, *optional*) – behavior on decode errors. Defaults to “strict”. Refer to stdtypes’ bytes.decode for details.
- **force_tty** (*bool*, *optional*) – force allocate a tty (ssh -tt). Defaults to False
- **stderr_merge** (*bool*, *optional*) – merge ssh subprocess stderr into stdout. Defaults to False.
- **stdout_loglevel** (*int*, *optional*) – log stdout with specific log level as well. Defaults to None, i.e. don’t log.
- **stderr_loglevel** (*int*, *optional*) – log stderr with specific log level as well. Defaults to None, i.e. don’t log.

Returns

stdout of the executed command if successful and otherwise an ExecutionError Exception

Return type List[str]

get_file (*remote_file*, *local_file*)

Get a file from the remote host

put_file (*local_file*, *remote_path*)

Put a file onto the remote host

add_port_forward (*remote_host*, *remote_port*)

forward command

remove_port_forward (*remote_host*, *remote_port*)

cancel command

connect ()

isconnected ()

disconnect ()

cleanup ()

__attrs_attrs__ = (Attribute(name='host', default=NOTHING, validator=<instance of vali

__dict__ = mappingproxy({'__module__': 'labgrid.util.ssh', '__doc__': 'SSHConnection

__eq__ (*other*)

Method generated by attrs for class SSHConnection.

__ge__ (*other*)

Method generated by attrs for class SSHConnection.

__gt__ (*other*)

Method generated by attrs for class SSHConnection.

```
__hash__ = None
__init__(host) → None
    Method generated by attrs for class SSHConnection.
__le__(other)
    Method generated by attrs for class SSHConnection.
__lt__(other)
    Method generated by attrs for class SSHConnection.
__module__ = 'labgrid.util.ssh'
__ne__(other)
    Method generated by attrs for class SSHConnection.
__repr__()
    Method generated by attrs for class SSHConnection.
__weakref__
    list of weak references to the object (if defined)
exception labgrid.util.ssh.ForwardError(msg)
    Bases: Exception
__attrs_attrs__ = (Attribute(name='msg', default=NOTHING, validator=<instance_of valid
__eq__(other)
    Method generated by attrs for class ForwardError.
__ge__(other)
    Method generated by attrs for class ForwardError.
__gt__(other)
    Method generated by attrs for class ForwardError.
__hash__ = None
__init__(msg) → None
    Method generated by attrs for class ForwardError.
__le__(other)
    Method generated by attrs for class ForwardError.
__lt__(other)
    Method generated by attrs for class ForwardError.
__module__ = 'labgrid.util.ssh'
__ne__(other)
    Method generated by attrs for class ForwardError.
__repr__()
    Method generated by attrs for class ForwardError.
__weakref__
    list of weak references to the object (if defined)
```

labgrid.util.timeout module

```
class labgrid.util.timeout.Timeout(timeout=120.0)
    Bases: object
```

Reperents a timeout (as a deadline)

`__attrs_post_init__()`

property remaining

property expired

`__attrs_attrs__ = (Attribute(name='timeout', default=120.0, validator=<instance of val`

`__dict__ = mappingproxy({'__module__': 'labgrid.util.timeout', '__doc__': 'Reperents`

`__init__(timeout=120.0) → None`

Method generated by attrs for class Timeout.

`__module__ = 'labgrid.util.timeout'`

`__repr__()`

Method generated by attrs for class Timeout.

`__weakref__`

list of weak references to the object (if defined)

labgrid.util.yaml module

This module contains the custom YAML load and dump functions and associated loader and dumper

class `labgrid.util.yaml.Loader(stream)`

Bases: `yaml.loader.SafeLoader`

`__module__ = 'labgrid.util.yaml'`

`yaml_constructors = {'tag:yaml.org,2002:null': <function SafeConstructor.construct_ya`

class `labgrid.util.yaml.Dumper(stream, default_style=None, default_flow_style=False, canon-
ical=None, indent=None, width=None, allow_unicode=None,
line_break=None, encoding=None, explicit_start=None, ex-
plicit_end=None, version=None, tags=None, sort_keys=True)`

Bases: `yaml.dumper.SafeDumper`

`__module__ = 'labgrid.util.yaml'`

`yaml_representers = {<class 'NoneType'>: <function SafeRepresenter.represent_none>, <`

`labgrid.util.yaml.load(stream)`

Wrapper for yaml load function with custom loader.

`labgrid.util.yaml.dump(data, stream=None)`

Wrapper for yaml dump function with custom dumper.

`labgrid.util.yaml.resolve_templates(data, mapping)`

Iterate recursively over data and call substitute(mapping) on all Templates.

9.1.2 Submodules

9.1.3 labgrid.binding module

exception `labgrid.binding.StateError(msg)`

Bases: `Exception`

`__attrs_attrs__ = (Attribute(name='msg', default=NOTHING, validator=<instance of valid`

```
__init__(msg) → None
    Method generated by attrs for class StateError.

__module__ = 'labgrid.binding'

__repr__()
    Method generated by attrs for class StateError.

__weakref__
    list of weak references to the object (if defined)
```

exception labgrid.binding.**BindingError**(msg)
Bases: Exception

```
__attrs_attrs__ = (Attribute(name='msg', default=NOTHING, validator=<instance_of valid

__init__(msg) → None
    Method generated by attrs for class BindingError.

__module__ = 'labgrid.binding'

__repr__()
    Method generated by attrs for class BindingError.

__weakref__
    list of weak references to the object (if defined)
```

class labgrid.binding.**BindingState**
Bases: enum.Enum

An enumeration.

```
error = -1
idle = 0
bound = 1
active = 2
__module__ = 'labgrid.binding'
```

class labgrid.binding.**BindingMixin**(target, name)
Bases: object

Handles the binding and activation of drivers and their supplying resources and drivers.

One client can be bound to many suppliers, and one supplier can be bound by many clients.

Conflicting access to one supplier can be avoided by deactivating conflicting clients before activation (using the `resolve_conflicts` callback).

```
bindings = {}

__attrs_post_init__()

property display_name

on_supplier_bound(supplier)
    Called by the Target after a new supplier has been bound

on_client_bound(client)
    Called by the Target after a new client has been bound

on_activate()
    Called by the Target when this object has been activated
```

on_deactivate()

Called by the Target when this object has been deactivated

resolve_conflicts() (*client*)

Called by the Target to allow this object to deactivate conflicting clients.

classmethod check_active() (*func*)

class NamedBinding (*value*)

Bases: object

Marks a binding (or binding set) as requiring an explicit name.

__init__ (*value*)

Initialize self. See help(type(self)) for accurate signature.

__repr__ ()

Return repr(self).

__dict__ = mappingproxy({'__module__': 'labgrid.binding', '__doc__': '\n Marks a

__module__ = 'labgrid.binding'

__weakref__

list of weak references to the object (if defined)

__attrs_attrs__ = (Attribute(name='target', default=NOTHING, validator=None, repr=True

__dict__ = mappingproxy({'__module__': 'labgrid.binding', '__doc__': '\n Handles the

__init__ (*target, name*) → None

Method generated by attrs for class BindingMixin.

__module__ = 'labgrid.binding'

__repr__ ()

Method generated by attrs for class BindingMixin.

__weakref__

list of weak references to the object (if defined)

9.1.4 labgrid.config module

Config convenience class

This class encapsulates access functions to the environment configuration

class labgrid.config.Config (*filename*)

Bases: object

__attrs_post_init__ ()

resolve_path (*path*)

Resolve an absolute path

Parameters *path* (*str*) – path to resolve

Returns the absolute path

Return type str

resolve_path_str_or_list (*path*)

Resolves a single path or multiple paths. Always returns a list (containing a single or multiple resolved paths).

Parameters `path` (*str*, *list*) – path(s) to resolve

Returns absolute path(s)

Return type `list`

Raises **TypeError** – if input is neither str nor list

get_tool (*tool*)

Retrieve an entry from the tools subkey

Parameters `tool` (*str*) – the tool to retrieve the path for

Returns path to the requested tools

Return type `str`

get_image_path (*kind*)

Retrieve an entry from the images subkey

Parameters `kind` (*str*) – the kind of the image to retrieve the path for

Returns path to the image

Return type `str`

Raises **KeyError** – if the requested image can not be found in the configuration

get_path (*kind*)

Retrieve an entry from the paths subkey

Parameters `kind` (*str*) – the type of path to retrieve the path for

Returns path to the path

Return type `str`

Raises **KeyError** – if the requested image can not be found in the configuration

get_option (*name*, *default=None*)

Retrieve an entry from the options subkey

Parameters

- **name** (*str*) – name of the option
- **default** (*str*) – A default parameter in case the option can not be found

Returns value of the option or default parameter

Return type `str`

Raises **KeyError** – if the requested image can not be found in the configuration

set_option (*name*, *value*)

Set an entry in the options subkey

Parameters

- **name** (*str*) – name of the option
- **value** (*str*) – the new value

get_target_option (*target*, *name*, *default=None*)

Retrieve an entry from the options subkey under the specified **target** subkey

Parameters

- **target** (*str*) – name of the target
- **name** (*str*) – name of the option
- **default** (*str*) – A default parameter in case the option can not be found

Returns value of the option or default parameter

Return type str

Raises **KeyError** – if the requested key can not be found in the configuration, or if the target can not be found in the configuration.

set_target_option (*target, name, value*)

Set an entry in the options subkey under the specified target subkey

Parameters

- **target** (*str*) – name of the target
- **name** (*str*) – name of the option
- **value** (*str*) – the new value

Raises **KeyError** – if the requested target can not be found in the configuration

get_targets ()

get_imports ()

Helper function that returns the list of all imports

Returns List of files which should be imported

Return type List

get_paths ()

Helper function that returns the subdict of all paths

Returns Dictionary containing all path definitions

Return type Dict

get_images ()

Helper function that returns the subdict of all images

Returns Dictionary containing all image definitions

Return type Dict

get_features ()

```
__attrs_attrs__ = (Attribute(name='filename', default=NOTHING, validator=<instance_of >
```

```
__dict__ = mappingproxy({'__module__': 'labgrid.config', '__attrs_post_init__': <fun
```

```
__init__ (filename) → None
```

Method generated by attrs for class Config.

```
__module__ = 'labgrid.config'
```

```
__repr__ ()
```

Method generated by attrs for class Config.

```
__weakref__
```

list of weak references to the object (if defined)

9.1.5 labgrid.consoleloggingreporter module

```
class labgrid.consoleloggingreporter.ConsoleLoggingReporter(logpath)
    Bases: object

    ConsoleLoggingReporter - Reporter that writes console log files

        Parameters logpath (str) – path to store the logfiles in

    instance = None

    classmethod start (path)
        starts the ConsoleLoggingReporter

    classmethod stop ()
        stops the ConsoleLoggingReporter

    __init__ (logpath)
        Initialize self. See help(type(self)) for accurate signature.

    get_logfile (event)
        Returns the correct file handle from cache or creates a new file handle

    notify (event)
        This is the callback function for steps

    __dict__ = mappingproxy({'__module__': 'labgrid.consoleloggingreporter', '__doc__':
    __module__ = 'labgrid.consoleloggingreporter'

    __weakref__
        list of weak references to the object (if defined)
```

9.1.6 labgrid.environment module

```
class labgrid.environment.Environment(config_file='config.yaml', interact=<built-in function
                                     input>)
    Bases: object

    An environment encapsulates targets.

    __attrs_post_init__ ()

    get_target (role: str = 'main') → labgrid.target.Target
        Returns the specified target or None if not found.

        Each target is initialized as needed.

    get_features ()

    get_target_features ()

    cleanup ()

    __attrs_attrs__ = (Attribute(name='config_file', default='config.yaml', validator=<ins
    __dict__ = mappingproxy({'__module__': 'labgrid.environment', '__doc__': 'An environ
    __init__ (config_file='config.yaml', interact=<built-in function input>) → None
        Method generated by attrs for class Environment.

    __module__ = 'labgrid.environment'

    __repr__ ()
        Method generated by attrs for class Environment.
```


`__weakref__`
list of weak references to the object (if defined)

9.1.7 labgrid.exceptions module

exception `labgrid.exceptions.NoConfigFoundError(msg)`

Bases: `Exception`

`__attrs_attrs__` = (`Attribute`(name='msg', default=NOTHING, validator=<instance_of valid

`__init__`(msg) → None

Method generated by attrs for class NoConfigFoundError.

`__module__` = 'labgrid.exceptions'

`__repr__`()

Method generated by attrs for class NoConfigFoundError.

`__weakref__`

list of weak references to the object (if defined)

exception `labgrid.exceptions.NoSupplierFoundError(msg, filter=None)`

Bases: `Exception`

`__attrs_attrs__` = (`Attribute`(name='msg', default=NOTHING, validator=<instance_of valid

`__init__`(msg, filter=None) → None

Method generated by attrs for class NoSupplierFoundError.

`__module__` = 'labgrid.exceptions'

`__repr__`()

Method generated by attrs for class NoSupplierFoundError.

`__weakref__`

list of weak references to the object (if defined)

exception `labgrid.exceptions.InvalidConfigError(msg)`

Bases: `Exception`

`__attrs_attrs__` = (`Attribute`(name='msg', default=NOTHING, validator=<instance_of valid

`__init__`(msg) → None

Method generated by attrs for class InvalidConfigError.

`__module__` = 'labgrid.exceptions'

`__repr__`()

Method generated by attrs for class InvalidConfigError.

`__weakref__`

list of weak references to the object (if defined)

exception `labgrid.exceptions.NoDriverFoundError(msg, filter=None)`

Bases: `labgrid.exceptions.NoSupplierFoundError`

`__attrs_attrs__` = (`Attribute`(name='msg', default=NOTHING, validator=<instance_of valid

`__init__`(msg, filter=None) → None

Method generated by attrs for class NoDriverFoundError.

`__module__` = 'labgrid.exceptions'

```
__repr__ ()
    Method generated by attrs for class NoDriverFoundError.

exception labgrid.exceptions.NoResourceFoundError (msg, filter=None)
    Bases: labgrid.exceptions.NoSupplierFoundError

    __attrs_attrs__ = (Attribute(name='msg', default=NOTHING, validator=<instance_of valid
    __init__ (msg, filter=None) → None
        Method generated by attrs for class NoResourceFoundError.

    __module__ = 'labgrid.exceptions'

    __repr__ ()
        Method generated by attrs for class NoResourceFoundError.

exception labgrid.exceptions.RegistrationError (msg)
    Bases: Exception

    __attrs_attrs__ = (Attribute(name='msg', default=NOTHING, validator=<instance_of valid
    __init__ (msg) → None
        Method generated by attrs for class RegistrationError.

    __module__ = 'labgrid.exceptions'

    __repr__ ()
        Method generated by attrs for class RegistrationError.

    __weakref__
        list of weak references to the object (if defined)
```

9.1.8 labgrid.factory module

```
class labgrid.factory.TargetFactory
    Bases: object

    __init__ ()
        Initialize self. See help(type(self)) for accurate signature.

    reg_resource (cls)
        Register a resource with the factory.

        Returns the class to allow using it as a decorator.

    reg_driver (cls)
        Register a driver with the factory.

        Returns the class to allow using it as a decorator.

    static normalize_config (config)

    make_resource (target, resource, name, args)

    make_driver (target, driver, name, args)

    make_target (name, config, *, env=None)

    class_from_string (string: str)

    __dict__ = mappingproxy({'__module__': 'labgrid.factory', '__init__': <function Targ
    __module__ = 'labgrid.factory'
```

__weakref__
list of weak references to the object (if defined)

`labgrid.factory.target_factory = <labgrid.factory.TargetFactory object>`
Global TargetFactory instance

This instance is used to register Resource and Driver classes so that Targets can be created automatically from YAML files.

9.1.9 labgrid.step module

class `labgrid.step.Steps`

Bases: `object`

__init__ ()
Initialize self. See `help(type(self))` for accurate signature.

get_current ()

get_new (*title, tag, source*)

push (*step*)

pop (*step*)

subscribe (*callback*)

unsubscribe (*callback*)

notify (*event*)

__dict__ = `mappingproxy({'__module__': 'labgrid.step', '__init__': <function Steps.__init__ at 0x7f8b1b1b1b1b>})`

__module__ = 'labgrid.step'

__weakref__
list of weak references to the object (if defined)

class `labgrid.step.StepEvent` (*step, data, *, resource=None, stream=False*)

Bases: `object`

__init__ (*step, data, *, resource=None, stream=False*)
Initialize self. See `help(type(self))` for accurate signature.

__str__ ()
Return `str(self)`.

__setitem__ (*k, v*)

merge (*other*)

property `age`

__dict__ = `mappingproxy({'__module__': 'labgrid.step', '__init__': <function StepEvent.__init__ at 0x7f8b1b1b1b1b>})`

__module__ = 'labgrid.step'

__weakref__
list of weak references to the object (if defined)

class `labgrid.step.Step` (*title, level, tag, source*)

Bases: `object`

__init__ (*title, level, tag, source*)
Initialize self. See `help(type(self))` for accurate signature.

```
__repr__()  
    Return repr(self).  
  
__str__()  
    Return str(self).  
  
property duration  
property status  
property is_active  
property is_done  
  
start()  
  
skip(reason)  
  
stop()  
  
__del__()  
  
__dict__ = mappingproxy({'__module__': 'labgrid.step', '__init__': <function Step.__init__>,  
__module__ = 'labgrid.step'  
  
__weakref__  
    list of weak references to the object (if defined)
```

```
labgrid.step.step(* , title=None, args=[], result=False, tag=None)
```

9.1.10 labgrid.stepreporter module

```
class labgrid.stepreporter.StepReporter  
    Bases: object  
  
    instance = None  
  
    classmethod start()  
        starts the StepReporter  
  
    classmethod stop()  
        stops the StepReporter  
  
    __init__()  
        Initialize self. See help(type(self)) for accurate signature.  
  
    static notify(event)  
  
    __dict__ = mappingproxy({'__module__': 'labgrid.stepreporter', 'instance': None, 'start': start,  
    __module__ = 'labgrid.stepreporter'  
  
    __weakref__  
        list of weak references to the object (if defined)
```

9.1.11 labgrid.target module

```
class labgrid.target.Target(name, env=None)  
    Bases: object  
  
    __attrs_post_init__()  
  
    interact(msg)
```

update_resources()

Iterate over all relevant resources and deactivate any active but unavailable resources.

await_resources(resources, timeout=None, avail=True)

Poll the given resources and wait until they are (un-)available.

Parameters

- **resources** (*List*) – the resources to poll
- **timeout** (*float*) – optional timeout
- **avail** (*bool*) – optionally wait until the resources are unavailable with avail=False

get_resource(cls, *, name=None, wait_avail=True)

Helper function to get a resource of the target. Returns the first valid resource found, otherwise a NoResourceFoundError is raised.

Arguments: cls – resource-class to return as a resource name – optional name to use as a filter wait_avail – wait for the resource to become available (default True)

get_active_driver(cls, *, name=None)

Helper function to get the active driver of the target. Returns the active driver found, otherwise None.

Arguments: cls – driver-class to return as a resource name – optional name to use as a filter

get_driver(cls, *, name=None, activate=True)

Helper function to get a driver of the target. Returns the first valid driver found, otherwise None.

Arguments: cls – driver-class to return as a resource name – optional name to use as a filter activate – activate the driver (default True)

__getitem__(key)

Syntactic sugar to access drivers by class (optionally filtered by name).

```
>>> target = Target('main')
>>> console = FakeConsoleDriver(target, 'console')
>>> target.activate(console)
>>> target[FakeConsoleDriver]
FakeConsoleDriver(target=Target(name='main', ...), name='console', ...)
>>> target[FakeConsoleDriver, 'console']
FakeConsoleDriver(target=Target(name='main', ...), name='console', ...)
```

set_binding_map(mapping)

Configure the binding name mapping for the next driver only.

bind_resource(resource)

Bind the resource to this target.

bind_driver(client)

Bind the driver to all suppliers (resources and other drivers).

Currently, we only support binding all suppliers at once.

bind(bindable)**activate(client, name=None)**

Activate the client by activating all bound suppliers. This may require deactivating other clients.

deactivate(client, name=None)

Recursively deactivate the client's clients and itself.

This is needed to ensure that no client has an inactive supplier.

deactivate_all_drivers()

Deactivates all drivers in reversed order they were activated

cleanup()

Clean up connected drivers and resources in reversed order

__attrs_attrs__ = (Attribute(name='name', default=NOTHING, validator=<instance_of vali

__dict__ = mappingproxy({'__module__': 'labgrid.target', '__attrs_post_init__': <fun

__init__(name, env=None) → None

Method generated by attrs for class Target.

__module__ = 'labgrid.target'

__repr__()

Method generated by attrs for class Target.

__weakref__

list of weak references to the object (if defined)

INDICES AND TABLES

- `genindex`
- `modindex`
- `search`

PYTHON MODULE INDEX

|

labgrid, 101
labgrid.autoinstall, 101
labgrid.autoinstall.main, 101
labgrid.binding, 191
labgrid.config, 193
labgrid.consoleloggingreporter, 196
labgrid.driver, 102
labgrid.driver.bareboxdriver, 104
labgrid.driver.commandmixin, 105
labgrid.driver.common, 106
labgrid.driver.consoleexpectmixin, 106
labgrid.driver.deditecrelaisdriver, 107
labgrid.driver.dockerdriver, 107
labgrid.driver.exception, 108
labgrid.driver.externalconsoledriver, 109
labgrid.driver.fake, 109
labgrid.driver.fastbootdriver, 111
labgrid.driver.filedigitaloutput, 112
labgrid.driver.flashromdriver, 112
labgrid.driver.gpiodriver, 113
labgrid.driver.lxaibusdriver, 113
labgrid.driver.modbusdriver, 114
labgrid.driver.onewiredriver, 114
labgrid.driver.openocddriver, 115
labgrid.driver.power, 102
labgrid.driver.power.apc, 102
labgrid.driver.power.digipower, 102
labgrid.driver.power.gude, 102
labgrid.driver.power.gude24, 102
labgrid.driver.power.gude8031, 102
labgrid.driver.power.gude8316, 103
labgrid.driver.power.netio, 103
labgrid.driver.power.netio_kshell, 103
labgrid.driver.power.sentry, 103
labgrid.driver.power.simplerest, 103
labgrid.driver.powerdriver, 115
labgrid.driver.pyvisadriver, 119
labgrid.driver.qemudriver, 120
labgrid.driver.quartushpsdriver, 121
labgrid.driver.resetdriver, 121
labgrid.driver.serialdigitaloutput, 122
labgrid.driver.serialdriver, 122
labgrid.driver.shelldriver, 123
labgrid.driver.sigrokdriver, 125
labgrid.driver.smallubootdriver, 127
labgrid.driver.sshdriver, 128
labgrid.driver.ubootdriver, 128
labgrid.driver.usbloader, 130
labgrid.driver.usbsdmuxdriver, 132
labgrid.driver.usbsdwireddriver, 132
labgrid.driver.usbstoragedriver, 133
labgrid.driver.usbtmc, 103
labgrid.driver.usbtmc.keysight_dsox2000, 103
labgrid.driver.usbtmc.tektronix_tds2000, 104
labgrid.driver.usbtmcdriver, 134
labgrid.driver.usbvideodriver, 134
labgrid.driver.xenadriver, 135
labgrid.environment, 196
labgrid.exceptions, 197
labgrid.factory, 198
labgrid.protocol, 135
labgrid.protocol.bootstrapprotocol, 135
labgrid.protocol.commandprotocol, 136
labgrid.protocol.consoleprotocol, 136
labgrid.protocol.digitaloutputprotocol, 137
labgrid.protocol.filesystemprotocol, 137
labgrid.protocol.filetransferprotocol, 137
labgrid.protocol.infoprotocol, 138
labgrid.protocol.linuxbootprotocol, 138
labgrid.protocol.mmioprotocol, 138
labgrid.protocol.powerprotocol, 139
labgrid.protocol.resetprotocol, 139
labgrid.provider, 139
labgrid.provider.fileprovider, 139
labgrid.provider.mediafileprovider, 140
labgrid.pytestplugin, 140
labgrid.pytestplugin.fixtures, 140
labgrid.pytestplugin.hooks, 140

labgrid.pytestplugin.reporter, [141](#)
labgrid.remote, [141](#)
labgrid.remote.authenticator, [141](#)
labgrid.remote.client, [141](#)
labgrid.remote.common, [142](#)
labgrid.remote.config, [145](#)
labgrid.remote.coordinator, [145](#)
labgrid.remote.exporter, [146](#)
labgrid.remote.scheduler, [152](#)
labgrid.resource, [152](#)
labgrid.resource.base, [152](#)
labgrid.resource.common, [154](#)
labgrid.resource.docker, [156](#)
labgrid.resource.ethernetport, [157](#)
labgrid.resource.flashrom, [159](#)
labgrid.resource.lxaiobus, [160](#)
labgrid.resource.modbus, [161](#)
labgrid.resource.networkservice, [161](#)
labgrid.resource.onewireport, [161](#)
labgrid.resource.power, [162](#)
labgrid.resource.pyvisa, [162](#)
labgrid.resource.remote, [163](#)
labgrid.resource.serialport, [169](#)
labgrid.resource.sigrok, [169](#)
labgrid.resource.suggest, [170](#)
labgrid.resource.udev, [170](#)
labgrid.resource.xenamanager, [176](#)
labgrid.resource.ykushpowerport, [177](#)
labgrid.step, [199](#)
labgrid.stepreporter, [200](#)
labgrid.strategy, [177](#)
labgrid.strategy.bareboxstrategy, [177](#)
labgrid.strategy.common, [178](#)
labgrid.strategy.dockerstrategy, [179](#)
labgrid.strategy.graphstrategy, [179](#)
labgrid.strategy.shellstrategy, [180](#)
labgrid.strategy.ubootstrategy, [181](#)
labgrid.target, [200](#)
labgrid.util, [181](#)
labgrid.util.agent, [182](#)
labgrid.util.agents, [181](#)
labgrid.util.agents.dummy, [181](#)
labgrid.util.agents.sysfsgpio, [182](#)
labgrid.util.agentwrapper, [183](#)
labgrid.util.atomic, [184](#)
labgrid.util.dict, [184](#)
labgrid.util.exceptions, [184](#)
labgrid.util.expect, [185](#)
labgrid.util.helper, [185](#)
labgrid.util.managedfile, [186](#)
labgrid.util.marker, [187](#)
labgrid.util.proxy, [187](#)
labgrid.util.qmp, [187](#)
labgrid.util.ssh, [188](#)
labgrid.util.timeout, [190](#)
labgrid.util.yaml, [191](#)

Symbols

__abstractmethods__	(lab- grid.driver.bareboxdriver.BareboxDriver attribute), 105	__abstractmethods__	(lab- grid.driver.openocddriver.OpenOCDDriver attribute), 115
__abstractmethods__	(lab- grid.driver.deditecrelaisdriver.DeditecRelaisDriver attribute), 107	__abstractmethods__	(lab- grid.driver.powerdriver.DigitalOutputPowerDriver attribute), 118
__abstractmethods__	(lab- grid.driver.dockerdriver.DockerDriver tribute), 108	__abstractmethods__	(lab- grid.driver.powerdriver.ExternalPowerDriver attribute), 117
__abstractmethods__	(lab- grid.driver.externalconsoledriver.ExternalConsoleDriver attribute), 109	__abstractmethods__	(lab- grid.driver.powerdriver.ManualPowerDriver attribute), 116
__abstractmethods__	(lab- grid.driver.fake.FakeCommandDriver tribute), 110	__abstractmethods__	(lab- grid.driver.powerdriver.NetworkPowerDriver attribute), 117
__abstractmethods__	(lab- grid.driver.fake.FakeConsoleDriver tribute), 110	__abstractmethods__	(lab- grid.driver.powerdriver.PDUDaemonDriver attribute), 119
__abstractmethods__	(lab- grid.driver.fake.FakeFileTransferDriver tribute), 110	__abstractmethods__	(lab- grid.driver.powerdriver.PowerResetMixin attribute), 115
__abstractmethods__	(lab- grid.driver.fake.FakePowerDriver tribute), 111	__abstractmethods__	(lab- grid.driver.powerdriver.SiSPMPowerDriver attribute), 116
__abstractmethods__	(lab- grid.driver.filedigitaloutput.FileDigitalOutputDriver tribute), 112	__abstractmethods__	(lab- grid.driver.powerdriver.USBPowerDriver tribute), 119
__abstractmethods__	(lab- grid.driver.flashromdriver.FlashromDriver tribute), 113	__abstractmethods__	(lab- grid.driver.powerdriver.YKUSHPowerDriver tribute), 118
__abstractmethods__	(lab- grid.driver.gpiodriver.GpioDigitalOutputDriver tribute), 113	__abstractmethods__	(lab- grid.driver.qemudriver.QEMUDriver tribute), 121
__abstractmethods__	(lab- grid.driver.lxaibusdriver.LXAIOBusPIODriver tribute), 114	__abstractmethods__	(lab- grid.driver.resetdriver.DigitalOutputResetDriver tribute), 121
__abstractmethods__	(lab- grid.driver.modbusdriver.ModbusCoilDriver tribute), 114	__abstractmethods__	(lab- grid.driver.serialdigitaloutput.SerialPortDigitalOutputDriver tribute), 122
__abstractmethods__	(lab- grid.driver.onewiredriver.OneWirePIODriver tribute), 115	__abstractmethods__	(lab- grid.driver.serialdriver.SerialDriver tribute), 121

__abstractmethods__ (labgrid.driver.shelldriver.ShellDriver attribute), 123	__abstractmethods__ (labgrid.protocol.mmioproto- col.MMIOProtocol attribute), 138
__abstractmethods__ (labgrid.driver.sigrokdriver.SigrokPowerDriver attribute), 125	__abstractmethods__ (labgrid.protocol.powerprotocol.PowerProtocol attribute), 139
__abstractmethods__ (labgrid.driver.smallubootdriver.SmallUBootDriver attribute), 127	__abstractmethods__ (labgrid.protocol.resetprotocol.ResetProtocol attribute), 139
__abstractmethods__ (labgrid.driver.sshdriver.SSHDriver attribute), 128	__abstractmethods__ (labgrid.provider.fileprovider.FileProvider attribute), 140
__abstractmethods__ (labgrid.driver.ubootdriver.UBootDriver attribute), 130	__abstractmethods__ (labgrid.provider.mediafileprovider.MediaFileProvider attribute), 140
__abstractmethods__ (labgrid.driver.usbloader.IMXUSBDriver attribute), 131	__attrs_attrs__ (labgrid.binding.BindingError attribute), 192
__abstractmethods__ (labgrid.driver.usbloader.MXSUSBDriver attribute), 130	__attrs_attrs__ (labgrid.binding.BindingMixin attribute), 193
__abstractmethods__ (labgrid.driver.usbloader.RKUSBDriver attribute), 131	__attrs_attrs__ (labgrid.binding.StateError attribute), 191
__abstractmethods__ (labgrid.driver.usbloader.UUUDriver attribute), 131	__attrs_attrs__ (labgrid.config.Config attribute), 195
__abstractmethods__ (labgrid.protocol.bootstrapprotocol.BootstrapProtocol attribute), 135	__attrs_attrs__ (labgrid.driver.bareboxdriver.BareboxDriver attribute), 105
__abstractmethods__ (labgrid.protocol.commandprotocol.CommandProtocol attribute), 136	__attrs_attrs__ (labgrid.driver.common.Driver attribute), 106
__abstractmethods__ (labgrid.protocol.consoleprotocol.ConsoleProtocol attribute), 137	__attrs_attrs__ (labgrid.driver.deditecrelaisdriver.DeditecRelaisDriver attribute), 107
__abstractmethods__ (labgrid.protocol.consoleprotocol.ConsoleProtocol.Client attribute), 136	__attrs_attrs__ (labgrid.driver.dockerdriver.DockerDriver attribute), 108
__abstractmethods__ (labgrid.protocol.digitaloutputprotocol.DigitalOutputProtocol attribute), 137	__attrs_attrs__ (labgrid.driver.exception.CleanUpError attribute), 109
__abstractmethods__ (labgrid.protocol.filesystemprotocol.FileSystemProtocol attribute), 137	__attrs_attrs__ (labgrid.driver.exception.ExecutionError attribute), 108
__abstractmethods__ (labgrid.protocol.filetransferprotocol.FileTransferProtocol attribute), 137	__attrs_attrs__ (labgrid.driver.externalconsoledriver.ExternalConsoleDriver attribute), 109
__abstractmethods__ (labgrid.protocol.fake.fakecommanddriver.FakeCommandDriver attribute), 110	__attrs_attrs__ (labgrid.driver.fake.FakeConsoleDriver attribute), 110
__abstractmethods__ (labgrid.protocol.fake.fakeconsoledriver.FakeConsoleDriver attribute), 110	__attrs_attrs__ (labgrid.driver.fake.FakeFileTransferDriver attribute), 110
__abstractmethods__ (labgrid.protocol.infoprotocol.InfoProtocol attribute), 138	
__abstractmethods__ (labgrid.protocol.linuxbootprotocol.LinuxBootProtocol attribute), 138	

<code>__attrs_attrs__</code> (lab- <code>grid.driver.fake.FakePowerDriver</code> attribute), 111	<code>__attrs_attrs__</code> (lab- <code>grid.driver.pyvisadriver.PyVISADriver</code> attribute), 120
<code>__attrs_attrs__</code> (lab- <code>grid.driver.fastbootdriver.AndroidFastbootDriver</code> attribute), 111	<code>__attrs_attrs__</code> (lab- <code>grid.driver.qemudriver.QEMUDriver</code> attribute), 121
<code>__attrs_attrs__</code> (lab- <code>grid.driver.filedigitaloutput.FileDigitalOutputDriver</code> attribute), 112	<code>__attrs_attrs__</code> (lab- <code>grid.driver.quartushpsdriver.QuartusHPSDriver</code> attribute), 121
<code>__attrs_attrs__</code> (lab- <code>grid.driver.flashromdriver.FlashromDriver</code> attribute), 113	<code>__attrs_attrs__</code> (lab- <code>grid.driver.resetdriver.DigitalOutputResetDriver</code> attribute), 121
<code>__attrs_attrs__</code> (lab- <code>grid.driver.gpiodriver.GpioDigitalOutputDriver</code> attribute), 113	<code>__attrs_attrs__</code> (lab- <code>grid.driver.serialdigitaloutput.SerialPortDigitalOutputDriver</code> attribute), 122
<code>__attrs_attrs__</code> (lab- <code>grid.driver.lxaiobusdriver.LXAIOBusPIODriver</code> attribute), 114	<code>__attrs_attrs__</code> (lab- <code>grid.driver.serialdriver.SerialDriver</code> attribute), 123
<code>__attrs_attrs__</code> (lab- <code>grid.driver.modbusdriver.ModbusCoilDriver</code> attribute), 114	<code>__attrs_attrs__</code> (lab- <code>grid.driver.shelldriver.ShellDriver</code> attribute), 125
<code>__attrs_attrs__</code> (lab- <code>grid.driver.onewiredriver.OneWirePIODriver</code> attribute), 115	<code>__attrs_attrs__</code> (lab- <code>grid.driver.sigrokdriver.SigrokCommon</code> attribute), 125
<code>__attrs_attrs__</code> (lab- <code>grid.driver.openocddriver.OpenOCDDriver</code> attribute), 115	<code>__attrs_attrs__</code> (lab- <code>grid.driver.sigrokdriver.SigrokDriver</code> attribute), 126
<code>__attrs_attrs__</code> (lab- <code>grid.driver.powerdriver.DigitalOutputPowerDriver</code> attribute), 118	<code>__attrs_attrs__</code> (lab- <code>grid.driver.sigrokdriver.SigrokPowerDriver</code> attribute), 126
<code>__attrs_attrs__</code> (lab- <code>grid.driver.powerdriver.ExternalPowerDriver</code> attribute), 117	<code>__attrs_attrs__</code> (lab- <code>grid.driver.smallubootdriver.SmallUBootDriver</code> attribute), 127
<code>__attrs_attrs__</code> (lab- <code>grid.driver.powerdriver.ManualPowerDriver</code> attribute), 116	<code>__attrs_attrs__</code> (lab- <code>grid.driver.sshdriver.SSHDriver</code> attribute), 128
<code>__attrs_attrs__</code> (lab- <code>grid.driver.powerdriver.NetworkPowerDriver</code> attribute), 117	<code>__attrs_attrs__</code> (lab- <code>grid.driver.ubootdriver.UBootDriver</code> attribute), 130
<code>__attrs_attrs__</code> (lab- <code>grid.driver.powerdriver.PDUDaemonDriver</code> attribute), 119	<code>__attrs_attrs__</code> (lab- <code>grid.driver.usbloader.IMXUSBDriver</code> attribute), 131
<code>__attrs_attrs__</code> (lab- <code>grid.driver.powerdriver.PowerResetMixin</code> attribute), 116	<code>__attrs_attrs__</code> (lab- <code>grid.driver.usbloader.MXSUSBDriver</code> attribute), 130
<code>__attrs_attrs__</code> (lab- <code>grid.driver.powerdriver.SiSPMPowerDriver</code> attribute), 116	<code>__attrs_attrs__</code> (lab- <code>grid.driver.usbloader.RKUSBDriver</code> attribute), 131
<code>__attrs_attrs__</code> (lab- <code>grid.driver.powerdriver.USBPowerDriver</code> attribute), 119	<code>__attrs_attrs__</code> (lab- <code>grid.driver.usbloader.UUUDriver</code> attribute), 131
<code>__attrs_attrs__</code> (lab- <code>grid.driver.powerdriver.YKUSHPowerDriver</code> attribute), 118	<code>__attrs_attrs__</code> (lab- <code>grid.driver.usbsdmuxdriver.USBSDMuxDriver</code> attribute), 132
<code>__attrs_attrs__</code> (lab-	<code>__attrs_attrs__</code> (lab-

<code>grid.driver.usbsdwiredriver.USBSDWireDriver</code>	<code>__attrs_attrs__</code>	<code>grid.remote.coordinator.ClientSession</code>	(lab-
attribute), 132		tribute), 146	
<code>__attrs_attrs__</code>	(lab-	<code>grid.remote.coordinator.ExporterSession</code>	(lab-
<code>grid.driver.usbstoragedriver.NetworkUSBStorageDriver</code>	<code>__attrs_attrs__</code>	tribute), 146	
attribute), 133		<code>__attrs_attrs__</code>	(lab-
<code>__attrs_attrs__</code>	(lab-	<code>grid.remote.coordinator.RemoteSession</code>	at-
<code>grid.driver.usbstoragedriver.USBStorageDriver</code>	<code>__attrs_attrs__</code>	tribute), 145	
attribute), 133		<code>__attrs_attrs__</code>	(lab-
<code>__attrs_attrs__</code>	(lab-	<code>grid.remote.coordinator.ResourceImport</code>	
<code>grid.driver.usbtmcdriver.USBTMCDriver</code>	<code>__attrs_attrs__</code>	tribute), 146	
attribute), 134		<code>__attrs_attrs__</code>	(lab-
<code>__attrs_attrs__</code>	(lab-	<code>grid.remote.exporter.EthernetPortExport</code>	
<code>grid.driver.usbviedriver.USBVideoDriver</code>	<code>__attrs_attrs__</code>	tribute), 150	
attribute), 134		<code>__attrs_attrs__</code>	(lab-
<code>__attrs_attrs__</code>	(lab-	<code>grid.remote.exporter.GPIOGenericExport</code>	
<code>grid.driver.xenadriver.XenaDriver</code>	tribute),	tribute), 151	
135		<code>__attrs_attrs__</code>	(lab-
<code>__attrs_attrs__</code>	(labgrid.environment.Environment	<code>grid.remote.exporter.LXAIOBusNodeExport</code>	
tribute), 196		tribute), 152	
<code>__attrs_attrs__</code>	(lab-	<code>__attrs_attrs__</code>	(lab-
<code>grid.exceptions.InvalidConfigError</code>	tribute),	<code>grid.remote.exporter.NetworkServiceExport</code>	
197		tribute), 151	
<code>__attrs_attrs__</code>	(lab-	<code>__attrs_attrs__</code>	(lab-
<code>grid.exceptions.NoConfigFoundError</code>	at-	<code>grid.remote.exporter.ResourceExport</code>	at-
tribute), 197		tribute), 147	
<code>__attrs_attrs__</code>	(lab-	<code>__attrs_attrs__</code>	(lab-
<code>grid.exceptions.NoDriverFoundError</code>	at-	<code>grid.remote.exporter.SerialPortExport</code>	at-
tribute), 197		tribute), 147	
<code>__attrs_attrs__</code>	(lab-	<code>__attrs_attrs__</code>	(lab-
<code>grid.exceptions.NoResourceFoundError</code>	at-	<code>grid.remote.exporter.SiSPMPowerPortExport</code>	
tribute), 198		tribute), 149	
<code>__attrs_attrs__</code>	(lab-	<code>__attrs_attrs__</code>	(lab-
<code>grid.exceptions.NoSupplierFoundError</code>	at-	<code>grid.remote.exporter.USBDebounceRelaisExport</code>	
tribute), 197		tribute), 150	
<code>__attrs_attrs__</code>	(lab-	<code>__attrs_attrs__</code>	(lab-
<code>grid.exceptions.RegistrationError</code>	tribute),	<code>grid.remote.exporter.USBEthernetExport</code>	
198		tribute), 148	
<code>__attrs_attrs__</code>	(lab-	<code>__attrs_attrs__</code>	(lab-
<code>grid.provider.mediafileprovider.MediaFileProvider</code>	<code>__attrs_attrs__</code>	<code>grid.remote.exporter.USBGenericExport</code>	
tribute), 140		tribute), 148	
<code>__attrs_attrs__</code>	(labgrid.remote.common.Place	<code>__attrs_attrs__</code>	(lab-
tribute), 143		<code>grid.remote.exporter.USBPowerPortExport</code>	
<code>__attrs_attrs__</code>	(lab-	tribute), 149	
<code>grid.remote.common.Reservation</code>	tribute),	<code>__attrs_attrs__</code>	(lab-
144		<code>grid.remote.exporter.USBSDMuxExport</code>	at-
<code>__attrs_attrs__</code>	(lab-	tribute), 149	
<code>grid.remote.common.ResourceEntry</code>	tribute),	<code>__attrs_attrs__</code>	(lab-
142		<code>grid.remote.exporter.USBSDWireExport</code>	at-
<code>__attrs_attrs__</code>	(lab-	tribute), 149	
<code>grid.remote.common.ResourceMatch</code>	tribute),	<code>__attrs_attrs__</code>	(lab-
143		<code>grid.remote.exporter.USBSigrokExport</code>	at-
<code>__attrs_attrs__</code>	(lab-	tribute), 148	
<code>grid.remote.config.ResourceConfig</code>	tribute),		
145			

<code>__attrs_attrs__</code> (<i>labgrid.remote.scheduler.TagSet</i> attribute), 152	<code>__attrs_attrs__</code> (<i>labgrid.resource.modbus.ModbusTCPCoil</i> attribute), 161
<code>__attrs_attrs__</code> (<i>labgrid.resource.base.EthernetInterface</i> attribute), 153	<code>__attrs_attrs__</code> (<i>labgrid.resource.networkservice.NetworkService</i> attribute), 161
<code>__attrs_attrs__</code> (<i>labgrid.resource.base.EthernetPort</i> attribute), 153	<code>__attrs_attrs__</code> (<i>labgrid.resource.onewireport.OneWirePIO</i> attribute), 161
<code>__attrs_attrs__</code> (<i>labgrid.resource.base.SerialPort</i> attribute), 153	<code>__attrs_attrs__</code> (<i>labgrid.resource.power.NetworkPowerPort</i> attribute), 162
<code>__attrs_attrs__</code> (<i>labgrid.resource.base.SysfsGPIO</i> attribute), 154	<code>__attrs_attrs__</code> (<i>labgrid.resource.power.PDUDaemonPort</i> attribute), 162
<code>__attrs_attrs__</code> (<i>labgrid.resource.common.ManagedResource</i> attribute), 155	<code>__attrs_attrs__</code> (<i>labgrid.resource.pyvisa.PyVISADevice</i> attribute), 163
<code>__attrs_attrs__</code> (<i>labgrid.resource.common.NetworkResource</i> attribute), 155	<code>__attrs_attrs__</code> (<i>labgrid.resource.remote.NetworkAlteraUSBBlaster</i> attribute), 165
<code>__attrs_attrs__</code> (<i>labgrid.resource.common.Resource</i> attribute), 154	<code>__attrs_attrs__</code> (<i>labgrid.resource.remote.NetworkAndroidFastboot</i> attribute), 164
<code>__attrs_attrs__</code> (<i>labgrid.resource.common.ResourceManager</i> attribute), 155	<code>__attrs_attrs__</code> (<i>labgrid.resource.remote.NetworkDeditecRelais8</i> attribute), 168
<code>__attrs_attrs__</code> (<i>labgrid.resource.docker.DockerDaemon</i> attribute), 157	<code>__attrs_attrs__</code> (<i>labgrid.resource.remote.NetworkIMXUSBLoader</i> attribute), 164
<code>__attrs_attrs__</code> (<i>labgrid.resource.docker.DockerManager</i> attribute), 156	<code>__attrs_attrs__</code> (<i>labgrid.resource.remote.NetworkLXAIOBusNode</i> attribute), 168
<code>__attrs_attrs__</code> (<i>labgrid.resource.ethernetport.EthernetPortManager</i> attribute), 158	<code>__attrs_attrs__</code> (<i>labgrid.resource.remote.NetworkLXAIOBusPIO</i> attribute), 168
<code>__attrs_attrs__</code> (<i>labgrid.resource.ethernetport.SNMPEthernetPort</i> attribute), 159	<code>__attrs_attrs__</code> (<i>labgrid.resource.remote.NetworkMXSUSBLoader</i> attribute), 164
<code>__attrs_attrs__</code> (<i>labgrid.resource.ethernetport.SNMPSwitch</i> attribute), 157	<code>__attrs_attrs__</code> (<i>labgrid.resource.remote.NetworkRKUSBLoader</i> attribute), 164
<code>__attrs_attrs__</code> (<i>labgrid.resource.flashrom.Flashrom</i> attribute), 159	<code>__attrs_attrs__</code> (<i>labgrid.resource.remote.NetworkSiSPMPowerPort</i> attribute), 167
<code>__attrs_attrs__</code> (<i>labgrid.resource.flashrom.NetworkFlashrom</i> attribute), 159	<code>__attrs_attrs__</code> (<i>labgrid.resource.remote.NetworkSigrokUSBDevice</i> attribute), 165
<code>__attrs_attrs__</code> (<i>labgrid.resource.lxaiobus.LXAIOBusNode</i> attribute), 160	<code>__attrs_attrs__</code> (<i>labgrid.resource.remote.NetworkSigrokUSBSerialDevice</i> attribute), 165
<code>__attrs_attrs__</code> (<i>labgrid.resource.lxaiobus.LXAIOBusNodeManager</i> attribute), 160	<code>__attrs_attrs__</code> (<i>labgrid.resource.remote.NetworkSysfsGPIO</i> attribute), 168
<code>__attrs_attrs__</code> (<i>labgrid.resource.lxaiobus.LXAIOBusPIO</i> attribute), 160	

<code>__attrs_attrs__</code> (labgrid.resource.remote.NetworkUSBMassStorage attribute), 166	<code>__attrs_attrs__</code> (labgrid.resource.udev.SiSPMPowerPort attribute), 175
<code>__attrs_attrs__</code> (labgrid.resource.remote.NetworkUSBPowerPort attribute), 167	<code>__attrs_attrs__</code> (labgrid.resource.udev.SigrokUSBDevice attribute), 173
<code>__attrs_attrs__</code> (labgrid.resource.remote.NetworkUSBSDMuxDevice attribute), 166	<code>__attrs_attrs__</code> (labgrid.resource.udev.SigrokUSBSerialDevice attribute), 174
<code>__attrs_attrs__</code> (labgrid.resource.remote.NetworkUSBSDWireDevice attribute), 166	<code>__attrs_attrs__</code> (labgrid.resource.udev.USBEthernetInterface attribute), 173
<code>__attrs_attrs__</code> (labgrid.resource.remote.NetworkUSBTMC attribute), 167	<code>__attrs_attrs__</code> (labgrid.resource.udev.USBMassStorage attribute), 171
<code>__attrs_attrs__</code> (labgrid.resource.remote.NetworkUSBVideo attribute), 167	<code>__attrs_attrs__</code> (labgrid.resource.udev.USBPowerPort attribute), 175
<code>__attrs_attrs__</code> (labgrid.resource.remote.RemotePlace attribute), 163	<code>__attrs_attrs__</code> (labgrid.resource.udev.USBResource attribute), 171
<code>__attrs_attrs__</code> (labgrid.resource.remote.RemotePlaceManager attribute), 163	<code>__attrs_attrs__</code> (labgrid.resource.udev.USBSDMuxDevice attribute), 175
<code>__attrs_attrs__</code> (labgrid.resource.remote.RemoteUSBResource attribute), 164	<code>__attrs_attrs__</code> (labgrid.resource.udev.USBSDWireDevice attribute), 174
<code>__attrs_attrs__</code> (labgrid.resource.serialport.NetworkSerialPort attribute), 169	<code>__attrs_attrs__</code> (labgrid.resource.udev.USBSerialPort attribute), 171
<code>__attrs_attrs__</code> (labgrid.resource.serialport.RawSerialPort attribute), 169	<code>__attrs_attrs__</code> (labgrid.resource.udev.USBTMC attribute), 176
<code>__attrs_attrs__</code> (labgrid.resource.sigrok.SigrokDevice attribute), 170	<code>__attrs_attrs__</code> (labgrid.resource.udev.USBVideo attribute), 175
<code>__attrs_attrs__</code> (labgrid.resource.udev.AlteraUSBBlaster attribute), 173	<code>__attrs_attrs__</code> (labgrid.resource.udev.UdevManager attribute), 170
<code>__attrs_attrs__</code> (labgrid.resource.udev.AndroidFastboot attribute), 172	<code>__attrs_attrs__</code> (labgrid.resource.xenamanager.XenaManager attribute), 176
<code>__attrs_attrs__</code> (labgrid.resource.udev.DeditecRelais8 attribute), 176	<code>__attrs_attrs__</code> (labgrid.resource.ykushpowerport.YKUSHPowerPort attribute), 177
<code>__attrs_attrs__</code> (labgrid.resource.udev.IMXUSBLoader attribute), 172	<code>__attrs_attrs__</code> (labgrid.strategy.bareboxstrategy.BareboxStrategy attribute), 177
<code>__attrs_attrs__</code> (labgrid.resource.udev.MXSUSBLoader attribute), 172	<code>__attrs_attrs__</code> (labgrid.strategy.common.Strategy attribute), 178
<code>__attrs_attrs__</code> (labgrid.resource.udev.RKUSBLoader attribute), 172	<code>__attrs_attrs__</code> (labgrid.strategy.common.StrategyError attribute), 178
	<code>__attrs_attrs__</code> (labgrid.strategy.dockerstrategy.DockerStrategy attribute), 178

- attribute*), 179
- `__attrs_attrs__` (*labgrid.strategy.shellstrategy.ShellStrategy attribute*), 180
- `__attrs_attrs__` (*labgrid.strategy.ubootstrategy.UBootStrategy attribute*), 181
- `__attrs_attrs__` (*labgrid.target.Target attribute*), 202
- `__attrs_attrs__` (*labgrid.util.exceptions.NoValidDriverError attribute*), 184
- `__attrs_attrs__` (*labgrid.util.helper.ProcessWrapper attribute*), 185
- `__attrs_attrs__` (*labgrid.util.managedfile.ManagedFile attribute*), 187
- `__attrs_attrs__` (*labgrid.util.qmp.QMPError attribute*), 188
- `__attrs_attrs__` (*labgrid.util.qmp.QMPMonitor attribute*), 187
- `__attrs_attrs__` (*labgrid.util.ssh.ForwardError attribute*), 190
- `__attrs_attrs__` (*labgrid.util.ssh.SSHConnection attribute*), 189
- `__attrs_attrs__` (*labgrid.util.timeout.Timeout attribute*), 191
- `__attrs_init__()` (*labgrid.remote.coordinator.RemoteSession method*), 145
- `__attrs_post_init__()` (*labgrid.binding.BindingMixin method*), 192
- `__attrs_post_init__()` (*labgrid.config.Config method*), 193
- `__attrs_post_init__()` (*labgrid.driver.bareboxdriver.BareboxDriver method*), 104
- `__attrs_post_init__()` (*labgrid.driver.commandmixin.CommandMixin method*), 105
- `__attrs_post_init__()` (*labgrid.driver.common.Driver method*), 106
- `__attrs_post_init__()` (*labgrid.driver.consoleexpectmixin.ConsoleExpectMixin method*), 106
- `__attrs_post_init__()` (*labgrid.driver.deditecrelaisdriver.DeditecRelaisDriver method*), 107
- `__attrs_post_init__()` (*labgrid.driver.dockerdriver.DockerDriver method*), 108
- `__attrs_post_init__()` (*labgrid.driver.externalconsoledriver.ExternalConsoleDriver method*), 109
- `__attrs_post_init__()` (*labgrid.driver.fake.FakeConsoleDriver method*), 109
- `__attrs_post_init__()` (*labgrid.driver.fastbootdriver.AndroidFastbootDriver method*), 111
- `__attrs_post_init__()` (*labgrid.driver.filedigitaloutput.FileDigitalOutputDriver method*), 112
- `__attrs_post_init__()` (*labgrid.driver.flashromdriver.FlashromDriver method*), 112
- `__attrs_post_init__()` (*labgrid.driver.gpiodriver.GpioDigitalOutputDriver method*), 113
- `__attrs_post_init__()` (*labgrid.driver.lxaibusdriver.LXAIOBusPIODriver method*), 113
- `__attrs_post_init__()` (*labgrid.driver.modbusdriver.ModbusCoilDriver method*), 114
- `__attrs_post_init__()` (*labgrid.driver.onewiredriver.OneWirePIODriver method*), 114
- `__attrs_post_init__()` (*labgrid.driver.openocddriver.OpenOCDDriver method*), 115
- `__attrs_post_init__()` (*labgrid.driver.powerdriver.DigitalOutputPowerDriver method*), 117
- `__attrs_post_init__()` (*labgrid.driver.powerdriver.NetworkPowerDriver method*), 117
- `__attrs_post_init__()` (*labgrid.driver.powerdriver.PDUDaemonDriver method*), 119
- `__attrs_post_init__()` (*labgrid.driver.powerdriver.PowerResetMixin method*), 115
- `__attrs_post_init__()` (*labgrid.driver.powerdriver.SiSPMPowerDriver method*), 116
- `__attrs_post_init__()` (*labgrid.driver.powerdriver.USBPowerDriver method*), 118
- `__attrs_post_init__()` (*labgrid.driver.powerdriver.YKUSHPowerDriver method*), 118
- `__attrs_post_init__()` (*labgrid.driver.pyvisadriver.PyVISADriver method*), 119
- `__attrs_post_init__()` (*labgrid.driver.qemudriver.QEMUDriver method*), 119

120		135	
<code>__attrs_post_init__()</code>	(<i>lab-grid.driver.quartushpsdriver.QuartusHPSDriver</i> method), 121	<code>__attrs_post_init__()</code>	(<i>lab-grid.environment.Environment</i> method), 196
<code>__attrs_post_init__()</code>	(<i>lab-grid.driver.resetdriver.DigitalOutputResetDriver</i> method), 121	<code>__attrs_post_init__()</code>	(<i>lab-grid.remote.common.ResourceEntry</i> method), 142
<code>__attrs_post_init__()</code>	(<i>lab-grid.driver.serialdigitaloutput.SerialPortDigitalOutputDriver</i> method), 122	<code>__attrs_post_init__()</code>	(<i>lab-grid.remote.config.ResourceConfig</i> method), 145
<code>__attrs_post_init__()</code>	(<i>lab-grid.driver.serialdriver.SerialDriver</i> method), 123	<code>__attrs_post_init__()</code>	(<i>lab-grid.remote.exporter.EthernetPortExport</i> method), 150
<code>__attrs_post_init__()</code>	(<i>lab-grid.driver.shelldriver.ShellDriver</i> method), 123	<code>__attrs_post_init__()</code>	(<i>lab-grid.remote.exporter.GPIOGenericExport</i> method), 151
<code>__attrs_post_init__()</code>	(<i>lab-grid.driver.sigrokdriver.SigrokCommon</i> method), 125	<code>__attrs_post_init__()</code>	(<i>lab-grid.remote.exporter.LXAIOPortNodeExport</i> method), 152
<code>__attrs_post_init__()</code>	(<i>lab-grid.driver.sshdriver.SSHDriver</i> method), 128	<code>__attrs_post_init__()</code>	(<i>lab-grid.remote.exporter.NetworkServiceExport</i> method), 151
<code>__attrs_post_init__()</code>	(<i>lab-grid.driver.ubootdriver.UBootDriver</i> method), 129	<code>__attrs_post_init__()</code>	(<i>lab-grid.remote.exporter.ResourceExport</i> method), 147
<code>__attrs_post_init__()</code>	(<i>lab-grid.driver.usbloader.IMXUSBDriver</i> method), 130	<code>__attrs_post_init__()</code>	(<i>lab-grid.remote.exporter.SerialPortExport</i> method), 147
<code>__attrs_post_init__()</code>	(<i>lab-grid.driver.usbloader.MXSUSBDriver</i> method), 130	<code>__attrs_post_init__()</code>	(<i>lab-grid.remote.exporter.SiSPMPowerPortExport</i> method), 149
<code>__attrs_post_init__()</code>	(<i>lab-grid.driver.usbloader.RKUSBDriver</i> method), 131	<code>__attrs_post_init__()</code>	(<i>lab-grid.remote.exporter.USBDeditecRelaisExport</i> method), 150
<code>__attrs_post_init__()</code>	(<i>lab-grid.driver.usbloader.UUUDriver</i> method), 131	<code>__attrs_post_init__()</code>	(<i>lab-grid.remote.exporter.USBEthernetExport</i> method), 148
<code>__attrs_post_init__()</code>	(<i>lab-grid.driver.usbsdmuxdriver.USBSDMuxDriver</i> method), 132	<code>__attrs_post_init__()</code>	(<i>lab-grid.remote.exporter.USBGenericExport</i> method), 148
<code>__attrs_post_init__()</code>	(<i>lab-grid.driver.usbsdwiredriver.USBSDWireDriver</i> method), 132	<code>__attrs_post_init__()</code>	(<i>lab-grid.remote.exporter.USBPowerPortExport</i> method), 149
<code>__attrs_post_init__()</code>	(<i>lab-grid.driver.usbstoragedriver.NetworkUSBStorageDriver</i> method), 133	<code>__attrs_post_init__()</code>	(<i>lab-grid.remote.exporter.USBSDMuxExport</i> method), 148
<code>__attrs_post_init__()</code>	(<i>lab-grid.driver.usbstoragedriver.USBStorageDriver</i> method), 133	<code>__attrs_post_init__()</code>	(<i>lab-grid.remote.exporter.USBSDWireExport</i> method), 149
<code>__attrs_post_init__()</code>	(<i>lab-grid.driver.usbtmcdriver.USBTMCDriver</i> method), 134	<code>__attrs_post_init__()</code>	(<i>lab-grid.remote.exporter.USBSigrokExport</i> method), 148
<code>__attrs_post_init__()</code>	(<i>lab-grid.driver.xenadriver.XenaDriver</i> method),	<code>__attrs_post_init__()</code>	(<i>lab-grid.resource.common.ManagedResource</i>

method), 155		method), 165	
<code>__attrs_post_init__()</code> (<i>lab-grid.resource.common.Resource</i> method), 154		<code>__attrs_post_init__()</code> (<i>lab-grid.resource.remote.NetworkSigrokUSBSerialDevice</i> method), 165	
<code>__attrs_post_init__()</code> (<i>lab-grid.resource.common.ResourceManager</i> method), 155		<code>__attrs_post_init__()</code> (<i>lab-grid.resource.remote.NetworkSysfsGPIO</i> method), 168	
<code>__attrs_post_init__()</code> (<i>lab-grid.resource.docker.DockerDaemon</i> method), 157		<code>__attrs_post_init__()</code> (<i>lab-grid.resource.remote.NetworkUSBMassStorage</i> method), 166	
<code>__attrs_post_init__()</code> (<i>lab-grid.resource.docker.DockerManager</i> method), 156		<code>__attrs_post_init__()</code> (<i>lab-grid.resource.remote.NetworkUSBPowerPort</i> method), 167	
<code>__attrs_post_init__()</code> (<i>lab-grid.resource.ethernetport.EthernetPortManager</i> method), 158		<code>__attrs_post_init__()</code> (<i>lab-grid.resource.remote.NetworkUSBSDMuxDevice</i> method), 166	
<code>__attrs_post_init__()</code> (<i>lab-grid.resource.ethernetport.SNMPEthernetPort</i> method), 159		<code>__attrs_post_init__()</code> (<i>lab-grid.resource.remote.NetworkUSBSDWireDevice</i> method), 166	
<code>__attrs_post_init__()</code> (<i>lab-grid.resource.ethernetport.SNMPSwitch</i> method), 157		<code>__attrs_post_init__()</code> (<i>lab-grid.resource.remote.NetworkUSBTMC</i> method), 167	
<code>__attrs_post_init__()</code> (<i>lab-grid.resource.lxaiobus.LXAIOBusNode</i> method), 160		<code>__attrs_post_init__()</code> (<i>lab-grid.resource.remote.NetworkUSBVideo</i> method), 167	
<code>__attrs_post_init__()</code> (<i>lab-grid.resource.lxaiobus.LXAIOBusNodeManager</i> method), 160		<code>__attrs_post_init__()</code> (<i>lab-grid.resource.remote.RemotePlace</i> method), 163	
<code>__attrs_post_init__()</code> (<i>lab-grid.resource.remote.NetworkAlteraUSBBlaster</i> method), 165		<code>__attrs_post_init__()</code> (<i>lab-grid.resource.remote.RemotePlaceManager</i> method), 163	
<code>__attrs_post_init__()</code> (<i>lab-grid.resource.remote.NetworkAndroidFastboot</i> method), 164		<code>__attrs_post_init__()</code> (<i>lab-grid.resource.serialport.RawSerialPort</i> method), 169	
<code>__attrs_post_init__()</code> (<i>lab-grid.resource.remote.NetworkDeditecRelais8</i> method), 168		<code>__attrs_post_init__()</code> (<i>lab-grid.resource.udev.DeditecRelais8</i> method), 176	
<code>__attrs_post_init__()</code> (<i>lab-grid.resource.remote.NetworkIMXUSBLoader</i> method), 164		<code>__attrs_post_init__()</code> (<i>lab-grid.resource.udev.SigrokUSBDevice</i> method), 173	
<code>__attrs_post_init__()</code> (<i>lab-grid.resource.remote.NetworkLXAIOBusNode</i> method), 168		<code>__attrs_post_init__()</code> (<i>lab-grid.resource.udev.SigrokUSBSerialDevice</i> method), 174	
<code>__attrs_post_init__()</code> (<i>lab-grid.resource.remote.NetworkMXSUSBLoader</i> method), 164		<code>__attrs_post_init__()</code> (<i>lab-grid.resource.udev.USBEthernetInterface</i> method), 173	
<code>__attrs_post_init__()</code> (<i>lab-grid.resource.remote.NetworkRKUSBLoader</i> method), 164		<code>__attrs_post_init__()</code> (<i>lab-grid.resource.udev.USBMassStorage</i> method), 171	
<code>__attrs_post_init__()</code> (<i>lab-grid.resource.remote.NetworkSiSPMPowerPort</i> method), 167		<code>__attrs_post_init__()</code> (<i>lab-grid.resource.udev.USBPowerPort</i> method), 175	
<code>__attrs_post_init__()</code> (<i>lab-grid.resource.remote.NetworkSigrokUSBDevice</i>		<code>__attrs_post_init__()</code> (<i>lab-grid.resource.udev.USBResource</i> method),	

- [170](#)
- [__attrs_post_init__\(\) \(labgrid.resource.udev.USBSDMuxDevice method\), 175](#)
- [__attrs_post_init__\(\) \(labgrid.resource.udev.USBSDWireDevice method\), 174](#)
- [__attrs_post_init__\(\) \(labgrid.resource.udev.USBSerialPort method\), 171](#)
- [__attrs_post_init__\(\) \(labgrid.resource.udev.USBTMC method\), 176](#)
- [__attrs_post_init__\(\) \(labgrid.resource.udev.USBVideo method\), 175](#)
- [__attrs_post_init__\(\) \(labgrid.resource.udev.UdevManager method\), 170](#)
- [__attrs_post_init__\(\) \(labgrid.strategy.bareboxstrategy.BareboxStrategy method\), 177](#)
- [__attrs_post_init__\(\) \(labgrid.strategy.common.Strategy method\), 178](#)
- [__attrs_post_init__\(\) \(labgrid.strategy.dockerstrategy.DockerStrategy method\), 179](#)
- [__attrs_post_init__\(\) \(labgrid.strategy.graphstrategy.GraphStrategy method\), 179](#)
- [__attrs_post_init__\(\) \(labgrid.strategy.shellstrategy.ShellStrategy method\), 180](#)
- [__attrs_post_init__\(\) \(labgrid.strategy.ubootstrategy.UBootStrategy method\), 181](#)
- [__attrs_post_init__\(\) \(labgrid.target.Target method\), 200](#)
- [__attrs_post_init__\(\) \(labgrid.util.managedfile.ManagedFile method\), 186](#)
- [__attrs_post_init__\(\) \(labgrid.util.qmp.QMPMonitor method\), 187](#)
- [__attrs_post_init__\(\) \(labgrid.util.ssh.SSHConnection method\), 188](#)
- [__attrs_post_init__\(\) \(labgrid.util.timeout.Timeout method\), 191](#)
- [__call__\(\) \(labgrid.driver.fastbootdriver.AndroidFastbootDriver method\), 111](#)
- [__call__\(\) \(labgrid.driver.flashromdriver.FlashromDriver method\), 112](#)
- [__call__\(\) \(labgrid.util.agentwrapper.MethodProxy method\), 183](#)
- [__del__\(\) \(labgrid.remote.exporter.SerialPortExport method\), 147](#)
- [__del__\(\) \(labgrid.step.Step method\), 200](#)
- [__del__\(\) \(labgrid.util.agents.sysfsgpio.GpioDigitalOutput method\), 182](#)
- [__del__\(\) \(labgrid.util.agentwrapper.AgentWrapper method\), 183](#)
- [__dict__ \(labgrid.autoinstall.main.Manager attribute\), 101](#)
- [__dict__ \(labgrid.binding.BindingMixin attribute\), 193](#)
- [__dict__ \(labgrid.binding.BindingMixin.NamedBinding attribute\), 193](#)
- [__dict__ \(labgrid.config.Config attribute\), 195](#)
- [__dict__ \(labgrid.consoleloggingreporter.ConsoleLoggingReporter attribute\), 196](#)
- [__dict__ \(labgrid.driver.commandmixin.CommandMixin attribute\), 106](#)
- [__dict__ \(labgrid.driver.consoleexpectmixin.ConsoleExpectMixin attribute\), 107](#)
- [__dict__ \(labgrid.environment.Environment attribute\), 196](#)
- [__dict__ \(labgrid.factory.TargetFactory attribute\), 198](#)
- [__dict__ \(labgrid.protocol.bootstrapprotocol.BootstrapProtocol attribute\), 135](#)
- [__dict__ \(labgrid.protocol.commandprotocol.CommandProtocol attribute\), 136](#)
- [__dict__ \(labgrid.protocol.consoleprotocol.ConsoleProtocol attribute\), 137](#)
- [__dict__ \(labgrid.protocol.consoleprotocol.ConsoleProtocol.Client attribute\), 136](#)
- [__dict__ \(labgrid.protocol.digitaloutputprotocol.DigitalOutputProtocol attribute\), 137](#)
- [__dict__ \(labgrid.protocol.filesystemprotocol.FileSystemProtocol attribute\), 137](#)
- [__dict__ \(labgrid.protocol.filetransferprotocol.FileTransferProtocol attribute\), 138](#)
- [__dict__ \(labgrid.protocol.infoprotocol.InfoProtocol attribute\), 138](#)
- [__dict__ \(labgrid.protocol.linuxbootprotocol.LinuxBootProtocol attribute\), 138](#)
- [__dict__ \(labgrid.protocol.mmioprotocol.MMIOProtocol attribute\), 139](#)
- [__dict__ \(labgrid.protocol.powerprotocol.PowerProtocol attribute\), 139](#)
- [__dict__ \(labgrid.protocol.resetprotocol.ResetProtocol attribute\), 139](#)
- [__dict__ \(labgrid.provider.fileprovider.FileProvider attribute\), 140](#)
- [__dict__ \(labgrid.pytestplugin.reporter.StepReporter attribute\), 141](#)
- [__dict__ \(labgrid.remote.common.Place attribute\), 144](#)
- [__dict__ \(labgrid.remote.common.Reservation attribute\), 144](#)

- `__dict__` (*labgrid.remote.common.ResourceEntry* attribute), 142
- `__dict__` (*labgrid.remote.common.ResourceMatch* attribute), 143
- `__dict__` (*labgrid.remote.config.ResourceConfig* attribute), 145
- `__dict__` (*labgrid.remote.coordinator.RemoteSession* attribute), 145
- `__dict__` (*labgrid.remote.scheduler.TagSet* attribute), 152
- `__dict__` (*labgrid.resource.common.ResourceManager* attribute), 155
- `__dict__` (*labgrid.resource.docker.DockerConstants* attribute), 156
- `__dict__` (*labgrid.resource.ethernetport.SNMPSwitch* attribute), 157
- `__dict__` (*labgrid.resource.suggest.Suggester* attribute), 170
- `__dict__` (*labgrid.step.Step* attribute), 200
- `__dict__` (*labgrid.step.StepEvent* attribute), 199
- `__dict__` (*labgrid.step.Steps* attribute), 199
- `__dict__` (*labgrid.stepreporter.StepReporter* attribute), 200
- `__dict__` (*labgrid.target.Target* attribute), 202
- `__dict__` (*labgrid.util.agent.Agent* attribute), 182
- `__dict__` (*labgrid.util.agents.sysfsgpio.GpioDigitalOutput* attribute), 182
- `__dict__` (*labgrid.util.agentwrapper.AgentWrapper* attribute), 184
- `__dict__` (*labgrid.util.agentwrapper.MethodProxy* attribute), 183
- `__dict__` (*labgrid.util.agentwrapper.ModuleProxy* attribute), 183
- `__dict__` (*labgrid.util.helper.ProcessWrapper* attribute), 185
- `__dict__` (*labgrid.util.managedfile.ManagedFile* attribute), 187
- `__dict__` (*labgrid.util.qmp.QMPMonitor* attribute), 187
- `__dict__` (*labgrid.util.ssh.SSHConnection* attribute), 189
- `__dict__` (*labgrid.util.timeout.Timeout* attribute), 191
- `__eq__` () (*labgrid.remote.common.ResourceMatch* method), 143
- `__eq__` () (*labgrid.remote.exporter.EthernetPortExport* method), 150
- `__eq__` () (*labgrid.remote.exporter.NetworkServiceExport* method), 151
- `__eq__` () (*labgrid.resource.base.EthernetPort* method), 153
- `__eq__` () (*labgrid.resource.ethernetport.EthernetPortManager* method), 158
- `__eq__` () (*labgrid.resource.ethernetport.SNMPEthernetPort* method), 159
- `__eq__` () (*labgrid.resource.ethernetport.SNMPSwitch* method), 157
- `__eq__` () (*labgrid.util.helper.ProcessWrapper* method), 186
- `__eq__` () (*labgrid.util.managedfile.ManagedFile* method), 187
- `__eq__` () (*labgrid.util.ssh.ForwardError* method), 190
- `__eq__` () (*labgrid.util.ssh.SSHConnection* method), 189
- `__ge__` () (*labgrid.remote.common.ResourceMatch* method), 143
- `__ge__` () (*labgrid.remote.exporter.EthernetPortExport* method), 150
- `__ge__` () (*labgrid.remote.exporter.NetworkServiceExport* method), 151
- `__ge__` () (*labgrid.resource.base.EthernetPort* method), 153
- `__ge__` () (*labgrid.resource.ethernetport.EthernetPortManager* method), 158
- `__ge__` () (*labgrid.resource.ethernetport.SNMPEthernetPort* method), 159
- `__ge__` () (*labgrid.resource.ethernetport.SNMPSwitch* method), 157
- `__ge__` () (*labgrid.util.helper.ProcessWrapper* method), 186
- `__ge__` () (*labgrid.util.managedfile.ManagedFile* method), 187
- `__ge__` () (*labgrid.util.ssh.ForwardError* method), 190
- `__ge__` () (*labgrid.util.ssh.SSHConnection* method), 189
- `__getattr__` () (*labgrid.util.agentwrapper.AgentWrapper* method), 183
- `__getattr__` () (*labgrid.util.agentwrapper.ModuleProxy* method), 183
- `__getitem__` () (*labgrid.target.Target* method), 201
- `__gt__` () (*labgrid.remote.common.ResourceMatch* method), 143
- `__gt__` () (*labgrid.remote.exporter.EthernetPortExport* method), 150
- `__gt__` () (*labgrid.remote.exporter.NetworkServiceExport* method), 151
- `__gt__` () (*labgrid.resource.base.EthernetPort* method), 153
- `__gt__` () (*labgrid.resource.ethernetport.EthernetPortManager* method), 158
- `__gt__` () (*labgrid.resource.ethernetport.SNMPEthernetPort* method), 159
- `__gt__` () (*labgrid.resource.ethernetport.SNMPSwitch* method), 157
- `__gt__` () (*labgrid.util.helper.ProcessWrapper* method), 186
- `__gt__` () (*labgrid.util.managedfile.ManagedFile* method), 187
- `__gt__` () (*labgrid.util.ssh.ForwardError* method), 190
- `__gt__` () (*labgrid.util.ssh.SSHConnection* method), 189

`method`), 187
`__gt__()` (`labgrid.util.ssh.ForwardError` method), 190
`__gt__()` (`labgrid.util.ssh.SSHConnection` method), 189
`__hash__` (`labgrid.remote.common.ResourceMatch` attribute), 143
`__hash__` (`labgrid.remote.exporter.EthernetPortExport` attribute), 150
`__hash__` (`labgrid.remote.exporter.NetworkServiceExport` attribute), 151
`__hash__` (`labgrid.resource.base.EthernetPort` attribute), 153
`__hash__` (`labgrid.resource.ethernetport.EthernetPortManager` attribute), 158
`__hash__` (`labgrid.resource.ethernetport.SNMPEthernetPort` attribute), 159
`__hash__` (`labgrid.resource.ethernetport.SNMPSwitch` attribute), 157
`__hash__` (`labgrid.util.helper.ProcessWrapper` attribute), 186
`__hash__` (`labgrid.util.managedfile.ManagedFile` attribute), 187
`__hash__` (`labgrid.util.ssh.ForwardError` attribute), 190
`__hash__` (`labgrid.util.ssh.SSHConnection` attribute), 189
`__init__()` (`labgrid.autoinstall.main.Handler` method), 101
`__init__()` (`labgrid.autoinstall.main.Manager` method), 101
`__init__()` (`labgrid.binding.BindingError` method), 192
`__init__()` (`labgrid.binding.BindingMixin` method), 193
`__init__()` (`labgrid.binding.BindingMixin.NamedBinding` method), 193
`__init__()` (`labgrid.binding.StateError` method), 191
`__init__()` (`labgrid.config.Config` method), 195
`__init__()` (`labgrid.consoleloggingreporter.ConsoleLoggingReporter` method), 196
`__init__()` (`labgrid.driver.bareboxdriver.BareboxDriver` method), 105
`__init__()` (`labgrid.driver.common.Driver` method), 106
`__init__()` (`labgrid.driver.deditecrelaisdriver.DeditecRelaisDriver` method), 107
`__init__()` (`labgrid.driver.dockerdriver.DockerDriver` method), 108
`__init__()` (`labgrid.driver.exception.CleanUpError` method), 109
`__init__()` (`labgrid.driver.exception.ExecutionError` method), 108
`__init__()` (`labgrid.driver.externalconsoledriver.ExternalConsoleDriver` method), 109
`__init__()` (`labgrid.driver.fake.FakeCommandDriver` method), 110
`__init__()` (`labgrid.driver.fake.FakeConsoleDriver` method), 110
`__init__()` (`labgrid.driver.fake.FakeFileTransferDriver` method), 110
`__init__()` (`labgrid.driver.fake.FakePowerDriver` method), 111
`__init__()` (`labgrid.driver.fastbootdriver.AndroidFastbootDriver` method), 111
`__init__()` (`labgrid.driver.filedigitaloutput.FileDigitalOutputDriver` method), 112
`__init__()` (`labgrid.driver.flashromdriver.FlashromDriver` method), 113
`__init__()` (`labgrid.driver.gpiodriver.GpioDigitalOutputDriver` method), 113
`__init__()` (`labgrid.driver.lxaiobusdriver.LXAIOBusPIODriver` method), 114
`__init__()` (`labgrid.driver.modbusdriver.ModbusCoilDriver` method), 114
`__init__()` (`labgrid.driver.onewiredriver.OneWirePIODriver` method), 115
`__init__()` (`labgrid.driver.openocddriver.OpenOCDDriver` method), 115
`__init__()` (`labgrid.driver.powerdriver.DigitalOutputPowerDriver` method), 118
`__init__()` (`labgrid.driver.powerdriver.ExternalPowerDriver` method), 117
`__init__()` (`labgrid.driver.powerdriver.ManualPowerDriver` method), 116
`__init__()` (`labgrid.driver.powerdriver.NetworkPowerDriver` method), 117
`__init__()` (`labgrid.driver.powerdriver.PDUDaemonDriver` method), 119
`__init__()` (`labgrid.driver.powerdriver.PowerResetMixin` method), 116
`__init__()` (`labgrid.driver.powerdriver.SiSPMPowerDriver` method), 116
`__init__()` (`labgrid.driver.powerdriver.USBPowerDriver` method), 119
`__init__()` (`labgrid.driver.powerdriver.YKUSHPowerDriver` method), 118
`__init__()` (`labgrid.driver.pyvisadriver.PyVISADriver` method), 120
`__init__()` (`labgrid.driver.qemudriver.QEMUDriver` method), 121
`__init__()` (`labgrid.driver.quartushpsdriver.QuartusHPSDriver` method), 121
`__init__()` (`labgrid.driver.resetdriver.DigitalOutputResetDriver` method), 121
`__init__()` (`labgrid.driver.serialdigitaloutput.SerialPortDigitalOutputDriver` method), 122
`__init__()` (`labgrid.driver.serialdriver.SerialDriver` method), 123

<code>__init__()</code> (<i>labgrid.driver.shelldriver.ShellDriver</i> method), 125	<code>__init__()</code> (<i>labgrid.pytestplugin.reporter.ColoredStepReporter</i> method), 141
<code>__init__()</code> (<i>labgrid.driver.sigrokdriver.SigrokCommon</i> method), 125	<code>__init__()</code> (<i>labgrid.pytestplugin.reporter.StepReporter</i> method), 141
<code>__init__()</code> (<i>labgrid.driver.sigrokdriver.SigrokDriver</i> method), 126	<code>__init__()</code> (<i>labgrid.remote.common.Place</i> method), 144
<code>__init__()</code> (<i>labgrid.driver.sigrokdriver.SigrokPowerDriver</i> method), 126	<code>__init__()</code> (<i>labgrid.remote.common.Reservation</i> method), 144
<code>__init__()</code> (<i>labgrid.driver.smallubootdriver.SmallUBOOTDriver</i> method), 127	<code>__init__()</code> (<i>labgrid.remote.common.ResourceEntry</i> method), 142
<code>__init__()</code> (<i>labgrid.driver.sshdriver.SSHDriver</i> method), 128	<code>__init__()</code> (<i>labgrid.remote.common.ResourceMatch</i> method), 143
<code>__init__()</code> (<i>labgrid.driver.ubootdriver.UBOOTDriver</i> method), 130	<code>__init__()</code> (<i>labgrid.remote.config.ResourceConfig</i> method), 145
<code>__init__()</code> (<i>labgrid.driver.usbloader.IMXUSBDriver</i> method), 131	<code>__init__()</code> (<i>labgrid.remote.coordinator.ClientSession</i> method), 146
<code>__init__()</code> (<i>labgrid.driver.usbloader.MXSUSBDriver</i> method), 130	<code>__init__()</code> (<i>labgrid.remote.coordinator.ExporterSession</i> method), 146
<code>__init__()</code> (<i>labgrid.driver.usbloader.RKUSBDriver</i> method), 131	<code>__init__()</code> (<i>labgrid.remote.coordinator.ResourceImport</i> method), 146
<code>__init__()</code> (<i>labgrid.driver.usbloader.UUUDriver</i> method), 132	<code>__init__()</code> (<i>labgrid.remote.exporter.EthernetPortExport</i> method), 150
<code>__init__()</code> (<i>labgrid.driver.usbsdmuxdriver.USBSDMuxDriver</i> method), 132	<code>__init__()</code> (<i>labgrid.remote.exporter.GPIOGenericExport</i> method), 151
<code>__init__()</code> (<i>labgrid.driver.usbsdwiredriver.USBSDWireDriver</i> method), 132	<code>__init__()</code> (<i>labgrid.remote.exporter.LXAIOBusNodeExport</i> method), 152
<code>__init__()</code> (<i>labgrid.driver.usbstoragedriver.NetworkUSBStorageDriver</i> method), 133	<code>__init__()</code> (<i>labgrid.remote.exporter.NetworkServiceExport</i> method), 151
<code>__init__()</code> (<i>labgrid.driver.usbstoragedriver.USBStorageDriver</i> method), 133	<code>__init__()</code> (<i>labgrid.remote.exporter.ResourceExport</i> method), 147
<code>__init__()</code> (<i>labgrid.driver.usbtmcdriver.USBTMCDriver</i> method), 134	<code>__init__()</code> (<i>labgrid.remote.exporter.SerialPortExport</i> method), 147
<code>__init__()</code> (<i>labgrid.driver.usbviedriver.USBVideoDriver</i> method), 134	<code>__init__()</code> (<i>labgrid.remote.exporter.SiSPMPowerPortExport</i> method), 149
<code>__init__()</code> (<i>labgrid.driver.xenadriver.XenaDriver</i> method), 135	<code>__init__()</code> (<i>labgrid.remote.exporter.USBDebounceRelaisExport</i> method), 150
<code>__init__()</code> (<i>labgrid.environment.Environment</i> method), 196	<code>__init__()</code> (<i>labgrid.remote.exporter.USBEthernetExport</i> method), 148
<code>__init__()</code> (<i>labgrid.exceptions.InvalidConfigError</i> method), 197	<code>__init__()</code> (<i>labgrid.remote.exporter.USBGenericExport</i> method), 148
<code>__init__()</code> (<i>labgrid.exceptions.NoConfigFoundError</i> method), 197	<code>__init__()</code> (<i>labgrid.remote.exporter.USBPowerPortExport</i> method), 149
<code>__init__()</code> (<i>labgrid.exceptions.NoDriverFoundError</i> method), 197	<code>__init__()</code> (<i>labgrid.remote.exporter.USBSDMuxExport</i> method), 149
<code>__init__()</code> (<i>labgrid.exceptions.NoResourceFoundError</i> method), 198	<code>__init__()</code> (<i>labgrid.remote.exporter.USBSDWireExport</i> method), 149
<code>__init__()</code> (<i>labgrid.exceptions.NoSupplierFoundError</i> method), 197	<code>__init__()</code> (<i>labgrid.remote.exporter.USBSigrokExport</i> method), 148
<code>__init__()</code> (<i>labgrid.exceptions.RegistrationError</i> method), 198	<code>__init__()</code> (<i>labgrid.remote.scheduler.TagSet</i> method), 152
<code>__init__()</code> (<i>labgrid.factory.TargetFactory</i> method), 198	<code>__init__()</code> (<i>labgrid.resource.base.EthernetInterface</i> method), 153
<code>__init__()</code> (<i>labgrid.provider.mediafileprovider.MediaFileProvider</i> method), 140	<code>__init__()</code> (<i>labgrid.resource.base.EthernetPort</i> method), 153

<code>__init__()</code> (<i>labgrid.resource.base.SerialPort</i> method), 153	<code>__init__()</code> (<i>labgrid.resource.remote.NetworkLXAIOPort</i> method), 168
<code>__init__()</code> (<i>labgrid.resource.base.SysfsGPIO</i> method), 154	<code>__init__()</code> (<i>labgrid.resource.remote.NetworkMXSUSBLoader</i> method), 164
<code>__init__()</code> (<i>labgrid.resource.common.ManagedResource</i> method), 155	<code>__init__()</code> (<i>labgrid.resource.remote.NetworkRKUSBLoader</i> method), 164
<code>__init__()</code> (<i>labgrid.resource.common.NetworkResource</i> method), 155	<code>__init__()</code> (<i>labgrid.resource.remote.NetworkSiSPMPowerPort</i> method), 167
<code>__init__()</code> (<i>labgrid.resource.common.Resource</i> method), 154	<code>__init__()</code> (<i>labgrid.resource.remote.NetworkSigrokUSBDevice</i> method), 165
<code>__init__()</code> (<i>labgrid.resource.common.ResourceManager</i> method), 155	<code>__init__()</code> (<i>labgrid.resource.remote.NetworkSigrokUSBSerialDevice</i> method), 165
<code>__init__()</code> (<i>labgrid.resource.docker.DockerDaemon</i> method), 157	<code>__init__()</code> (<i>labgrid.resource.remote.NetworkSysfsGPIO</i> method), 168
<code>__init__()</code> (<i>labgrid.resource.docker.DockerManager</i> method), 156	<code>__init__()</code> (<i>labgrid.resource.remote.NetworkUSBMassStorage</i> method), 166
<code>__init__()</code> (<i>labgrid.resource.ethernetport.EthernetPortManager</i> method), 158	<code>__init__()</code> (<i>labgrid.resource.remote.NetworkUSBPowerPort</i> method), 167
<code>__init__()</code> (<i>labgrid.resource.ethernetport.SNMPEthernetPort</i> method), 159	<code>__init__()</code> (<i>labgrid.resource.remote.NetworkUSBSDMuxDevice</i> method), 166
<code>__init__()</code> (<i>labgrid.resource.ethernetport.SNMPSwitch</i> method), 157	<code>__init__()</code> (<i>labgrid.resource.remote.NetworkUSBSDWireDevice</i> method), 166
<code>__init__()</code> (<i>labgrid.resource.flashrom.Flashrom</i> method), 159	<code>__init__()</code> (<i>labgrid.resource.remote.NetworkUSBTMC</i> method), 167
<code>__init__()</code> (<i>labgrid.resource.flashrom.NetworkFlashrom</i> method), 159	<code>__init__()</code> (<i>labgrid.resource.remote.NetworkUSBVideo</i> method), 167
<code>__init__()</code> (<i>labgrid.resource.lxaiobus.LXAIOPortNode</i> method), 160	<code>__init__()</code> (<i>labgrid.resource.remote.RemotePlace</i> method), 163
<code>__init__()</code> (<i>labgrid.resource.lxaiobus.LXAIOPortNodeManager</i> method), 160	<code>__init__()</code> (<i>labgrid.resource.remote.RemotePlaceManager</i> method), 163
<code>__init__()</code> (<i>labgrid.resource.lxaiobus.LXAIOPortPIO</i> method), 160	<code>__init__()</code> (<i>labgrid.resource.remote.RemoteUSBResource</i> method), 164
<code>__init__()</code> (<i>labgrid.resource.modbus.ModbusTCPCoil</i> method), 161	<code>__init__()</code> (<i>labgrid.resource.serialport.NetworkSerialPort</i> method), 169
<code>__init__()</code> (<i>labgrid.resource.networkservice.NetworkService</i> method), 161	<code>__init__()</code> (<i>labgrid.resource.serialport.RawSerialPort</i> method), 169
<code>__init__()</code> (<i>labgrid.resource.onewireport.OneWirePIO</i> method), 162	<code>__init__()</code> (<i>labgrid.resource.sigrok.SigrokDevice</i> method), 170
<code>__init__()</code> (<i>labgrid.resource.power.NetworkPowerPort</i> method), 162	<code>__init__()</code> (<i>labgrid.resource.suggest.Suggester</i> method), 170
<code>__init__()</code> (<i>labgrid.resource.power.PDUDaemonPort</i> method), 162	<code>__init__()</code> (<i>labgrid.resource.udev.AlteraUSBBlaster</i> method), 173
<code>__init__()</code> (<i>labgrid.resource.pyvisa.PyVISADevice</i> method), 163	<code>__init__()</code> (<i>labgrid.resource.udev.AndroidFastboot</i> method), 172
<code>__init__()</code> (<i>labgrid.resource.remote.NetworkAlteraUSBBlaster</i> method), 165	<code>__init__()</code> (<i>labgrid.resource.udev.DeditecRelais8</i> method), 176
<code>__init__()</code> (<i>labgrid.resource.remote.NetworkAndroidFastboot</i> method), 164	<code>__init__()</code> (<i>labgrid.resource.udev.IMXUSBLoader</i> method), 172
<code>__init__()</code> (<i>labgrid.resource.remote.NetworkDeditecRelais8</i> method), 168	<code>__init__()</code> (<i>labgrid.resource.udev.MXSUSBLoader</i> method), 172
<code>__init__()</code> (<i>labgrid.resource.remote.NetworkIMXUSBLoader</i> method), 164	<code>__init__()</code> (<i>labgrid.resource.udev.RKUSBLoader</i> method), 172
<code>__init__()</code> (<i>labgrid.resource.remote.NetworkLXAIOPortNode</i> method), 168	<code>__init__()</code> (<i>labgrid.resource.udev.SiSPMPowerPort</i> method), 175

`__init__()` (*labgrid.resource.udev.SigrokUSBDevice* method), 173
`__init__()` (*labgrid.resource.udev.SigrokUSBSerialDevice* method), 174
`__init__()` (*labgrid.resource.udev.USBEthernetInterface* method), 173
`__init__()` (*labgrid.resource.udev.USBMassStorage* method), 171
`__init__()` (*labgrid.resource.udev.USBPowerPort* method), 175
`__init__()` (*labgrid.resource.udev.USBResource* method), 171
`__init__()` (*labgrid.resource.udev.USBSDMuxDevice* method), 175
`__init__()` (*labgrid.resource.udev.USBSDWireDevice* method), 174
`__init__()` (*labgrid.resource.udev.USBSerialPort* method), 171
`__init__()` (*labgrid.resource.udev.USBTMC* method), 176
`__init__()` (*labgrid.resource.udev.USBVideo* method), 176
`__init__()` (*labgrid.resource.udev.UdevManager* method), 170
`__init__()` (*labgrid.resource.xenamananager.XenaManager* method), 176
`__init__()` (*labgrid.resource.ykushpowerport.YKUSHPowerPort* method), 177
`__init__()` (*labgrid.step.Step* method), 199
`__init__()` (*labgrid.step.StepEvent* method), 199
`__init__()` (*labgrid.step.Steps* method), 199
`__init__()` (*labgrid.stepreporter.StepReporter* method), 200
`__init__()` (*labgrid.strategy.bareboxstrategy.BareboxStrategy* method), 177
`__init__()` (*labgrid.strategy.common.Strategy* method), 178
`__init__()` (*labgrid.strategy.common.StrategyError* method), 178
`__init__()` (*labgrid.strategy.dockerstrategy.DockerStrategy* method), 179
`__init__()` (*labgrid.strategy.shellstrategy.ShellStrategy* method), 180
`__init__()` (*labgrid.strategy.ubootstrategy.UBootStrategy* method), 181
`__init__()` (*labgrid.target.Target* method), 202
`__init__()` (*labgrid.util.agent.Agent* method), 182
`__init__()` (*labgrid.util.agents.sysfsgpio.GpioDigitalOutput* method), 182
`__init__()` (*labgrid.util.agentwrapper.AgentWrapper* method), 183
`__init__()` (*labgrid.util.agentwrapper.MethodProxy* method), 183
`__init__()` (*labgrid.util.agentwrapper.ModuleProxy* method), 183
`__init__()` (*labgrid.util.exceptions.NoValidDriverError* method), 184
`__init__()` (*labgrid.util.expect.PtxExpect* method), 185
`__init__()` (*labgrid.util.helper.ProcessWrapper* method), 186
`__init__()` (*labgrid.util.managedfile.ManagedFile* method), 187
`__init__()` (*labgrid.util.qmp.QMPError* method), 188
`__init__()` (*labgrid.util.qmp.QMPMonitor* method), 187
`__init__()` (*labgrid.util.ssh.ForwardError* method), 190
`__init__()` (*labgrid.util.ssh.SSHConnection* method), 190
`__init__()` (*labgrid.util.timeout.Timeout* method), 191
`__le__()` (*labgrid.remote.common.ResourceMatch* method), 143
`__le__()` (*labgrid.remote.exporter.EthernetPortExport* method), 150
`__le__()` (*labgrid.remote.exporter.NetworkServiceExport* method), 151
`__le__()` (*labgrid.resource.base.EthernetPort* method), 153
`__le__()` (*labgrid.resource.ethernetport.EthernetPortManager* method), 158
`__le__()` (*labgrid.resource.ethernetport.SNMPEthernetPort* method), 159
`__le__()` (*labgrid.resource.ethernetport.SNMPSwitch* method), 157
`__le__()` (*labgrid.util.helper.ProcessWrapper* method), 186
`__le__()` (*labgrid.util.managedfile.ManagedFile* method), 187
`__le__()` (*labgrid.util.ssh.ForwardError* method), 190
`__le__()` (*labgrid.util.ssh.SSHConnection* method), 190
`__lt__()` (*labgrid.remote.common.ResourceMatch* method), 143
`__lt__()` (*labgrid.remote.exporter.EthernetPortExport* method), 150
`__lt__()` (*labgrid.remote.exporter.NetworkServiceExport* method), 151
`__lt__()` (*labgrid.resource.base.EthernetPort* method), 153
`__lt__()` (*labgrid.resource.ethernetport.EthernetPortManager* method), 158
`__lt__()` (*labgrid.resource.ethernetport.SNMPEthernetPort* method), 159
`__lt__()` (*labgrid.resource.ethernetport.SNMPSwitch* method), 157

- `__lt__()` (*labgrid.util.helper.ProcessWrapper method*), 186
- `__lt__()` (*labgrid.util.managedfile.ManagedFile method*), 187
- `__lt__()` (*labgrid.util.ssh.ForwardError method*), 190
- `__lt__()` (*labgrid.util.ssh.SSHConnection method*), 190
- `__module__` (*labgrid.autoinstall.main.Handler attribute*), 101
- `__module__` (*labgrid.autoinstall.main.Manager attribute*), 101
- `__module__` (*labgrid.binding.BindingError attribute*), 192
- `__module__` (*labgrid.binding.BindingMixin attribute*), 193
- `__module__` (*labgrid.binding.BindingMixin.NamedBinding attribute*), 193
- `__module__` (*labgrid.binding.BindingState attribute*), 192
- `__module__` (*labgrid.binding.StateError attribute*), 192
- `__module__` (*labgrid.config.Config attribute*), 195
- `__module__` (*labgrid.consoleloggingreporter.ConsoleLoggingReporter attribute*), 196
- `__module__` (*labgrid.driver.bareboxdriver.BareboxDriver attribute*), 105
- `__module__` (*labgrid.driver.commandmixin.CommandMixin attribute*), 106
- `__module__` (*labgrid.driver.common.Driver attribute*), 106
- `__module__` (*labgrid.driver.consoleexpectmixin.ConsoleExpectMixin attribute*), 107
- `__module__` (*labgrid.driver.deditecrelaisdriver.DeditecRelaisDriver attribute*), 107
- `__module__` (*labgrid.driver.dockerdriver.DockerDriver attribute*), 108
- `__module__` (*labgrid.driver.exception.CleanUpError attribute*), 109
- `__module__` (*labgrid.driver.exception.ExecutionError attribute*), 108
- `__module__` (*labgrid.driver.externalconsoledriver.ExternalConsoleDriver attribute*), 109
- `__module__` (*labgrid.driver.fake.FakeCommandDriver attribute*), 110
- `__module__` (*labgrid.driver.fake.FakeConsoleDriver attribute*), 110
- `__module__` (*labgrid.driver.fake.FakeFileTransferDriver attribute*), 110
- `__module__` (*labgrid.driver.fake.FakePowerDriver attribute*), 111
- `__module__` (*labgrid.driver.fastbootdriver.AndroidFastbootDriver attribute*), 111
- `__module__` (*labgrid.driver.filedigitaloutput.FileDigitalOutputDriver attribute*), 112
- `__module__` (*labgrid.driver.flashromdriver.FlashromDriver attribute*), 113
- `__module__` (*labgrid.driver.gpiodriver.GpioDigitalOutputDriver attribute*), 113
- `__module__` (*labgrid.driver.lxaiobusdriver.LXAIOBusPIODriver attribute*), 114
- `__module__` (*labgrid.driver.modbusdriver.ModbusCoilDriver attribute*), 114
- `__module__` (*labgrid.driver.onewiredriver.OneWirePIODriver attribute*), 115
- `__module__` (*labgrid.driver.openocddriver.OpenOCDDriver attribute*), 115
- `__module__` (*labgrid.driver.powerdriver.DigitalOutputPowerDriver attribute*), 118
- `__module__` (*labgrid.driver.powerdriver.ExternalPowerDriver attribute*), 117
- `__module__` (*labgrid.driver.powerdriver.ManualPowerDriver attribute*), 116
- `__module__` (*labgrid.driver.powerdriver.NetworkPowerDriver attribute*), 117
- `__module__` (*labgrid.driver.powerdriver.PDUDaemonDriver attribute*), 119
- `__module__` (*labgrid.driver.powerdriver.PowerResetMixin attribute*), 116
- `__module__` (*labgrid.driver.powerdriver.SiSPMPowerDriver attribute*), 116
- `__module__` (*labgrid.driver.powerdriver.USBPowerDriver attribute*), 119
- `__module__` (*labgrid.driver.powerdriver.YKUSHPowerDriver attribute*), 118
- `__module__` (*labgrid.driver.pyvisadriver.PyVISADriver attribute*), 120
- `__module__` (*labgrid.driver.qemudriver.QEMUDriver attribute*), 121
- `__module__` (*labgrid.driver.quartushpsdriver.QuartusHPSDriver attribute*), 121
- `__module__` (*labgrid.driver.resetdriver.DigitalOutputResetDriver attribute*), 122
- `__module__` (*labgrid.driver.serialdigitaloutput.SerialPortDigitalOutputDriver attribute*), 122
- `__module__` (*labgrid.driver.serialdriver.SerialDriver attribute*), 123
- `__module__` (*labgrid.driver.shelldriver.ShellDriver attribute*), 125
- `__module__` (*labgrid.driver.sigrokdriver.SigrokCommon attribute*), 125
- `__module__` (*labgrid.driver.sigrokdriver.SigrokDriver attribute*), 126
- `__module__` (*labgrid.driver.sigrokdriver.SigrokPowerDriver attribute*), 126
- `__module__` (*labgrid.driver.smallubootdriver.SmallUBootDriver attribute*), 127
- `__module__` (*labgrid.driver.sshdriver.SSHDriver attribute*), 128

- `__module__` (`labgrid.driver.ubootdriver.UBootDriver` attribute), 130
- `__module__` (`labgrid.driver.usbloader.IMXUSBDriver` attribute), 131
- `__module__` (`labgrid.driver.usbloader.MXSUSBDriver` attribute), 130
- `__module__` (`labgrid.driver.usbloader.RKUSBDriver` attribute), 131
- `__module__` (`labgrid.driver.usbloader.UUUDriver` attribute), 132
- `__module__` (`labgrid.driver.usbsdmuxdriver.USBSDMuxDriver` attribute), 132
- `__module__` (`labgrid.driver.usbsdwiredriver.USBSDWireDriver` attribute), 132
- `__module__` (`labgrid.driver.usbstoragedriver.Mode` attribute), 133
- `__module__` (`labgrid.driver.usbstoragedriver.NetworkUSBStorageDriver` attribute), 133
- `__module__` (`labgrid.driver.usbstoragedriver.USBStorageDriver` attribute), 133
- `__module__` (`labgrid.driver.usbtmcdriver.USBTMCDriver` attribute), 134
- `__module__` (`labgrid.driver.usbvideodriver.USBVideoDriver` attribute), 135
- `__module__` (`labgrid.driver.xenadriver.XenaDriver` attribute), 135
- `__module__` (`labgrid.environment.Environment` attribute), 196
- `__module__` (`labgrid.exceptions.InvalidConfigError` attribute), 197
- `__module__` (`labgrid.exceptions.NoConfigFoundError` attribute), 197
- `__module__` (`labgrid.exceptions.NoDriverFoundError` attribute), 197
- `__module__` (`labgrid.exceptions.NoResourceFoundError` attribute), 198
- `__module__` (`labgrid.exceptions.NoSupplierFoundError` attribute), 197
- `__module__` (`labgrid.exceptions.RegistrationError` attribute), 198
- `__module__` (`labgrid.factory.TargetFactory` attribute), 198
- `__module__` (`labgrid.protocol.bootstrapprotocol.BootstrapProtocol` attribute), 135
- `__module__` (`labgrid.protocol.commandprotocol.CommandProtocol` attribute), 136
- `__module__` (`labgrid.protocol.consoleprotocol.ConsoleProtocol` attribute), 137
- `__module__` (`labgrid.protocol.consoleprotocol.ConsoleProtocolClient` attribute), 136
- `__module__` (`labgrid.protocol.digitaloutputprotocol.DigitalOutputProtocol` attribute), 137
- `__module__` (`labgrid.protocol.filesystemprotocol.FileSystemProtocol` attribute), 137
- `__module__` (`labgrid.protocol.filetransferprotocol.FileTransferProtocol` attribute), 138
- `__module__` (`labgrid.protocol.infoprotocol.InfoProtocol` attribute), 138
- `__module__` (`labgrid.protocol.linuxbootprotocol.LinuxBootProtocol` attribute), 138
- `__module__` (`labgrid.protocol.mmioprotocol.MMIOProtocol` attribute), 139
- `__module__` (`labgrid.protocol.powerprotocol.PowerProtocol` attribute), 139
- `__module__` (`labgrid.protocol.resetprotocol.ResetProtocol` attribute), 139
- `__module__` (`labgrid.provider.fileprovider.FileProvider` attribute), 140
- `__module__` (`labgrid.provider.mediafileprovider.MediaFileProvider` attribute), 140
- `__module__` (`labgrid.pytestplugin.reporter.ColoredStepReporter` attribute), 141
- `__module__` (`labgrid.pytestplugin.reporter.StepReporter` attribute), 141
- `__module__` (`labgrid.remote.client.Error` attribute), 141
- `__module__` (`labgrid.remote.client.ServerError` attribute), 142
- `__module__` (`labgrid.remote.client.UserError` attribute), 142
- `__module__` (`labgrid.remote.common.Place` attribute), 144
- `__module__` (`labgrid.remote.common.Reservation` attribute), 144
- `__module__` (`labgrid.remote.common.ReservationState` attribute), 144
- `__module__` (`labgrid.remote.common.ResourceEntry` attribute), 142
- `__module__` (`labgrid.remote.common.ResourceMatch` attribute), 143
- `__module__` (`labgrid.remote.config.ResourceConfig` attribute), 145
- `__module__` (`labgrid.remote.coordinator.Action` attribute), 145
- `__module__` (`labgrid.remote.coordinator.ClientSession` attribute), 146
- `__module__` (`labgrid.remote.coordinator.ExporterSession` attribute), 146
- `__module__` (`labgrid.remote.coordinator.RemoteSession` attribute), 145
- `__module__` (`labgrid.remote.coordinator.ResourceImport` attribute), 146
- `__module__` (`labgrid.remote.exporter.BrokenResourceError` attribute), 147
- `__module__` (`labgrid.remote.exporter.EthernetPortExport` attribute), 150
- `__module__` (`labgrid.remote.exporter.ExporterError` attribute), 146

<code>__module__ (labgrid.remote.exporter.GPIOGenericExport</code> <code>attribute), 151</code>	<code>__module__ (labgrid.resource.ethernetport.SNMPSwitch</code> <code>attribute), 157</code>
<code>__module__ (labgrid.remote.exporter.LXAIOBusNodeExport</code> <code>attribute), 152</code>	<code>__module__ (labgrid.resource.flashrom.Flashrom at-</code> <code>tribute), 159</code>
<code>__module__ (labgrid.remote.exporter.NetworkServiceExport</code> <code>attribute), 151</code>	<code>__module__ (labgrid.resource.flashrom.NetworkFlashrom</code> <code>attribute), 159</code>
<code>__module__ (labgrid.remote.exporter.ResourceExport</code> <code>attribute), 147</code>	<code>__module__ (labgrid.resource.lxaibus.LXAIOBusNode</code> <code>attribute), 160</code>
<code>__module__ (labgrid.remote.exporter.SerialPortExport</code> <code>attribute), 147</code>	<code>__module__ (labgrid.resource.lxaibus.LXAIOBusNodeManager</code> <code>attribute), 160</code>
<code>__module__ (labgrid.remote.exporter.SiSPMPowerPortExport</code> <code>attribute), 149</code>	<code>__module__ (labgrid.resource.lxaibus.LXAIOBusPIO</code> <code>attribute), 160</code>
<code>__module__ (labgrid.remote.exporter.USBDebounceRelaisExport</code> <code>attribute), 150</code>	<code>__module__ (labgrid.resource.modbus.ModbusTCPCoil</code> <code>attribute), 161</code>
<code>__module__ (labgrid.remote.exporter.USBEthernetExport</code> <code>attribute), 148</code>	<code>__module__ (labgrid.resource.networkservice.NetworkService</code> <code>attribute), 161</code>
<code>__module__ (labgrid.remote.exporter.USBGenericExport</code> <code>attribute), 148</code>	<code>__module__ (labgrid.resource.onewirereport.OneWirePIO</code> <code>attribute), 162</code>
<code>__module__ (labgrid.remote.exporter.USBPowerPortExport</code> <code>attribute), 150</code>	<code>__module__ (labgrid.resource.power.NetworkPowerPort</code> <code>attribute), 162</code>
<code>__module__ (labgrid.remote.exporter.USBSDMuxExport</code> <code>attribute), 149</code>	<code>__module__ (labgrid.resource.power.PDUDaemonPort</code> <code>attribute), 162</code>
<code>__module__ (labgrid.remote.exporter.USBSDWireExport</code> <code>attribute), 149</code>	<code>__module__ (labgrid.resource.pyvisa.PyVISADevice</code> <code>attribute), 163</code>
<code>__module__ (labgrid.remote.exporter.USBSigrokExport</code> <code>attribute), 148</code>	<code>__module__ (labgrid.resource.remote.NetworkAlteraUSBBlaster</code> <code>attribute), 165</code>
<code>__module__ (labgrid.remote.scheduler.TagSet at-</code> <code>tribute), 152</code>	<code>__module__ (labgrid.resource.remote.NetworkAndroidFastboot</code> <code>attribute), 164</code>
<code>__module__ (labgrid.resource.base.EthernetInterface</code> <code>attribute), 153</code>	<code>__module__ (labgrid.resource.remote.NetworkDebounceRelais8</code> <code>attribute), 168</code>
<code>__module__ (labgrid.resource.base.EthernetPort at-</code> <code>tribute), 153</code>	<code>__module__ (labgrid.resource.remote.NetworkIMXUSBLoader</code> <code>attribute), 164</code>
<code>__module__ (labgrid.resource.base.SerialPort at-</code> <code>tribute), 153</code>	<code>__module__ (labgrid.resource.remote.NetworkLXAIOBusNode</code> <code>attribute), 168</code>
<code>__module__ (labgrid.resource.base.SysfsGPIO at-</code> <code>tribute), 154</code>	<code>__module__ (labgrid.resource.remote.NetworkLXAIOBusPIO</code> <code>attribute), 169</code>
<code>__module__ (labgrid.resource.common.ManagedResource</code> <code>attribute), 155</code>	<code>__module__ (labgrid.resource.remote.NetworkMXSUSBLoader</code> <code>attribute), 164</code>
<code>__module__ (labgrid.resource.common.NetworkResource</code> <code>attribute), 155</code>	<code>__module__ (labgrid.resource.remote.NetworkRKUSBLoader</code> <code>attribute), 165</code>
<code>__module__ (labgrid.resource.common.Resource at-</code> <code>tribute), 154</code>	<code>__module__ (labgrid.resource.remote.NetworkSiSPMPowerPort</code> <code>attribute), 167</code>
<code>__module__ (labgrid.resource.common.ResourceManager</code> <code>attribute), 155</code>	<code>__module__ (labgrid.resource.remote.NetworkSigrokUSBDevice</code> <code>attribute), 165</code>
<code>__module__ (labgrid.resource.docker.DockerConstants</code> <code>attribute), 156</code>	<code>__module__ (labgrid.resource.remote.NetworkSigrokUSBSerialDevice</code> <code>attribute), 165</code>
<code>__module__ (labgrid.resource.docker.DockerDaemon</code> <code>attribute), 157</code>	<code>__module__ (labgrid.resource.remote.NetworkSysfsGPIO</code> <code>attribute), 168</code>
<code>__module__ (labgrid.resource.docker.DockerManager</code> <code>attribute), 156</code>	<code>__module__ (labgrid.resource.remote.NetworkUSBMassStorage</code> <code>attribute), 166</code>
<code>__module__ (labgrid.resource.ethernetport.EthernetPortManager</code> <code>attribute), 158</code>	<code>__module__ (labgrid.resource.remote.NetworkUSBPowerPort</code> <code>attribute), 167</code>
<code>__module__ (labgrid.resource.ethernetport.SNMPEthernetPort</code> <code>attribute), 159</code>	<code>__module__ (labgrid.resource.remote.NetworkUSBSDMuxDevice</code> <code>attribute), 166</code>

- `__module__` (`labgrid.resource.remote.NetworkUSBSDWireDevice` attribute), 166
- `__module__` (`labgrid.resource.remote.NetworkUSBVideoDevice` attribute), 176
- `__module__` (`labgrid.resource.remote.NetworkUSBTMC` attribute), 167
- `__module__` (`labgrid.resource.remote.NetworkUSBVideo` attribute), 167
- `__module__` (`labgrid.resource.remote.RemotePlace` attribute), 163
- `__module__` (`labgrid.resource.remote.RemotePlaceManager` attribute), 163
- `__module__` (`labgrid.resource.remote.RemoteUSBResource` attribute), 164
- `__module__` (`labgrid.resource.serialport.NetworkSerialPort` attribute), 169
- `__module__` (`labgrid.resource.serialport.RawSerialPort` attribute), 169
- `__module__` (`labgrid.resource.sigrok.SigrokDevice` attribute), 170
- `__module__` (`labgrid.resource.suggest.Suggester` attribute), 170
- `__module__` (`labgrid.resource.udev.AlteraUSBBlaster` attribute), 173
- `__module__` (`labgrid.resource.udev.AndroidFastboot` attribute), 172
- `__module__` (`labgrid.resource.udev.DeditecRelais8` attribute), 176
- `__module__` (`labgrid.resource.udev.IMXUSBLoader` attribute), 172
- `__module__` (`labgrid.resource.udev.MXSUSBLoader` attribute), 172
- `__module__` (`labgrid.resource.udev.RKUSBLoader` attribute), 172
- `__module__` (`labgrid.resource.udev.SiSPMPowerPort` attribute), 175
- `__module__` (`labgrid.resource.udev.SigrokUSBDevice` attribute), 173
- `__module__` (`labgrid.resource.udev.SigrokUSBSerialDevice` attribute), 174
- `__module__` (`labgrid.resource.udev.USBEthernetInterface` attribute), 173
- `__module__` (`labgrid.resource.udev.USBMassStorage` attribute), 171
- `__module__` (`labgrid.resource.udev.USBPowerPort` attribute), 175
- `__module__` (`labgrid.resource.udev.USBResource` attribute), 171
- `__module__` (`labgrid.resource.udev.USBSDMuxDevice` attribute), 175
- `__module__` (`labgrid.resource.udev.USBSDWireDevice` attribute), 174
- `__module__` (`labgrid.resource.udev.USBSerialPort` attribute), 171
- `__module__` (`labgrid.resource.udev.USBTMC` attribute), 176
- `__module__` (`labgrid.resource.udev.USBVideo` attribute), 176
- `__module__` (`labgrid.resource.udev.UdevManager` attribute), 170
- `__module__` (`labgrid.resource.xenamanager.XenaManager` attribute), 176
- `__module__` (`labgrid.resource.ykushpowerport.YKUSHPowerPort` attribute), 177
- `__module__` (`labgrid.step.Step` attribute), 200
- `__module__` (`labgrid.step.StepEvent` attribute), 199
- `__module__` (`labgrid.step.Steps` attribute), 199
- `__module__` (`labgrid.stepreporter.StepReporter` attribute), 200
- `__module__` (`labgrid.strategy.bareboxstrategy.BareboxStrategy` attribute), 177
- `__module__` (`labgrid.strategy.bareboxstrategy.Status` attribute), 177
- `__module__` (`labgrid.strategy.common.Strategy` attribute), 178
- `__module__` (`labgrid.strategy.common.StrategyError` attribute), 178
- `__module__` (`labgrid.strategy.dockerstrategy.DockerStrategy` attribute), 179
- `__module__` (`labgrid.strategy.dockerstrategy.Status` attribute), 179
- `__module__` (`labgrid.strategy.graphstrategy.GraphStrategy` attribute), 180
- `__module__` (`labgrid.strategy.graphstrategy.GraphStrategyError` attribute), 179
- `__module__` (`labgrid.strategy.graphstrategy.GraphStrategyRuntimeError` attribute), 179
- `__module__` (`labgrid.strategy.graphstrategy.InvalidGraphStrategyError` attribute), 179
- `__module__` (`labgrid.strategy.shellstrategy.ShellStrategy` attribute), 180
- `__module__` (`labgrid.strategy.shellstrategy.Status` attribute), 180
- `__module__` (`labgrid.strategy.ubootstrategy.Status` attribute), 181
- `__module__` (`labgrid.strategy.ubootstrategy.UBootStrategy` attribute), 181
- `__module__` (`labgrid.target.Target` attribute), 202
- `__module__` (`labgrid.util.agent.Agent` attribute), 182
- `__module__` (`labgrid.util.agents.sysfsgpio.GpioDigitalOutput` attribute), 182
- `__module__` (`labgrid.util.agentwrapper.AgentError` attribute), 183
- `__module__` (`labgrid.util.agentwrapper.AgentException` attribute), 183
- `__module__` (`labgrid.util.agentwrapper.AgentWrapper` attribute), 184
- `__module__` (`labgrid.util.agentwrapper.MethodProxy` attribute), 183
- `__module__` (`labgrid.util.agentwrapper.ModuleProxy` attribute), 183

attribute), 183
 __module__ (labgrid.util.exceptions.NoValidDriverError attribute), 184
 __module__ (labgrid.util.expect.PtxExpect attribute), 185
 __module__ (labgrid.util.helper.ProcessWrapper attribute), 186
 __module__ (labgrid.util.managedfile.ManagedFile attribute), 187
 __module__ (labgrid.util.qmp.QMPError attribute), 188
 __module__ (labgrid.util.qmp.QMPMonitor attribute), 187
 __module__ (labgrid.util.ssh.ForwardError attribute), 190
 __module__ (labgrid.util.ssh.SSHConnection attribute), 190
 __module__ (labgrid.util.timeout.Timeout attribute), 191
 __module__ (labgrid.util.yaml.Dumper attribute), 191
 __module__ (labgrid.util.yaml.Loader attribute), 191
 __ne__ () (labgrid.remote.common.ResourceMatch method), 143
 __ne__ () (labgrid.remote.exporter.EthernetPortExport method), 150
 __ne__ () (labgrid.remote.exporter.NetworkServiceExport method), 151
 __ne__ () (labgrid.resource.base.EthernetPort method), 153
 __ne__ () (labgrid.resource.ethernetport.EthernetPortManager method), 158
 __ne__ () (labgrid.resource.ethernetport.SNMPEthernetPort method), 159
 __ne__ () (labgrid.resource.ethernetport.SNMPSwitch method), 157
 __ne__ () (labgrid.util.helper.ProcessWrapper method), 186
 __ne__ () (labgrid.util.managedfile.ManagedFile method), 187
 __ne__ () (labgrid.util.ssh.ForwardError method), 190
 __ne__ () (labgrid.util.ssh.SSHConnection method), 190
 __repr__ () (labgrid.binding.BindingError method), 192
 __repr__ () (labgrid.binding.BindingMixin method), 193
 __repr__ () (labgrid.binding.BindingMixin.NamedBinding method), 193
 __repr__ () (labgrid.binding.StateError method), 192
 __repr__ () (labgrid.config.Config method), 195
 __repr__ () (labgrid.driver.bareboxdriver.BareboxDriver method), 105
 __repr__ () (labgrid.driver.common.Driver method), 106
 __repr__ () (labgrid.driver.deditecrelaisdriver.DeditecRelaisDriver method), 107
 __repr__ () (labgrid.driver.dockerdriver.DockerDriver method), 108
 __repr__ () (labgrid.driver.exception.CleanUpError method), 109
 __repr__ () (labgrid.driver.exception.ExecutionError method), 109
 __repr__ () (labgrid.driver.externalconsoledriver.ExternalConsoleDriver method), 109
 __repr__ () (labgrid.driver.fake.FakeCommandDriver method), 110
 __repr__ () (labgrid.driver.fake.FakeConsoleDriver method), 110
 __repr__ () (labgrid.driver.fake.FakeFileTransferDriver method), 110
 __repr__ () (labgrid.driver.fake.FakePowerDriver method), 111
 __repr__ () (labgrid.driver.fastbootdriver.AndroidFastbootDriver method), 112
 __repr__ () (labgrid.driver.filedigitaloutput.FileDigitalOutputDriver method), 112
 __repr__ () (labgrid.driver.flashromdriver.FlashromDriver method), 113
 __repr__ () (labgrid.driver.gpiodriver.GpioDigitalOutputDriver method), 113
 __repr__ () (labgrid.driver.lxaiobusdriver.LXAIOPiODriver method), 114
 __repr__ () (labgrid.driver.modbusdriver.ModbusCoilDriver method), 114
 __repr__ () (labgrid.driver.onewiredriver.OneWirePiODriver method), 115
 __repr__ () (labgrid.driver.openocddriver.OpenOCDDriver method), 115
 __repr__ () (labgrid.driver.powerdriver.DigitalOutputPowerDriver method), 118
 __repr__ () (labgrid.driver.powerdriver.ExternalPowerDriver method), 117
 __repr__ () (labgrid.driver.powerdriver.ManualPowerDriver method), 116
 __repr__ () (labgrid.driver.powerdriver.NetworkPowerDriver method), 117
 __repr__ () (labgrid.driver.powerdriver.PDUDaemonDriver method), 119
 __repr__ () (labgrid.driver.powerdriver.PowerResetMixin method), 116
 __repr__ () (labgrid.driver.powerdriver.SiSPMPowerDriver method), 116
 __repr__ () (labgrid.driver.powerdriver.USBPowerDriver method), 119
 __repr__ () (labgrid.driver.powerdriver.YKUSHPowerDriver method), 118
 __repr__ () (labgrid.driver.pyvisadriver.PyVISADriver method), 120

<code>__repr__()</code> (<code>labgrid.driver.qemudriver.QEMUDriver</code> method), 121	<code>__repr__()</code> (<code>labgrid.exceptions.NoResourceFoundError</code> method), 198
<code>__repr__()</code> (<code>labgrid.driver.quartushpsdriver.QuartusHPSDriver</code> method), 121	<code>__repr__()</code> (<code>labgrid.exceptions.NoSupplierFoundError</code> method), 197
<code>__repr__()</code> (<code>labgrid.driver.resetdriver.DigitalOutputResetDriver</code> method), 122	<code>__repr__()</code> (<code>labgrid.exceptions.RegistrationError</code> method), 198
<code>__repr__()</code> (<code>labgrid.driver.serialdigitaloutput.SerialPortDigitalOutputDriver</code> method), 122	<code>__repr__()</code> (<code>labgrid.provider.mediafileprovider.MediaFileProvider</code> method), 140
<code>__repr__()</code> (<code>labgrid.driver.serialdriver.SerialDriver</code> method), 123	<code>__repr__()</code> (<code>labgrid.remote.common.Place</code> method), 144
<code>__repr__()</code> (<code>labgrid.driver.shelldriver.ShellDriver</code> method), 125	<code>__repr__()</code> (<code>labgrid.remote.common.Reservation</code> method), 144
<code>__repr__()</code> (<code>labgrid.driver.sigrokdriver.SigrokCommon</code> method), 125	<code>__repr__()</code> (<code>labgrid.remote.common.ResourceEntry</code> method), 142
<code>__repr__()</code> (<code>labgrid.driver.sigrokdriver.SigrokDriver</code> method), 126	<code>__repr__()</code> (<code>labgrid.remote.common.ResourceMatch</code> method), 143
<code>__repr__()</code> (<code>labgrid.driver.sigrokdriver.SigrokPowerDriver</code> method), 126	<code>__repr__()</code> (<code>labgrid.remote.config.ResourceConfig</code> method), 145
<code>__repr__()</code> (<code>labgrid.driver.smallubootdriver.SmallUBOOTDriver</code> method), 128	<code>__repr__()</code> (<code>labgrid.remote.coordinator.ClientSession</code> method), 146
<code>__repr__()</code> (<code>labgrid.driver.sshdriver.SSHDriver</code> method), 128	<code>__repr__()</code> (<code>labgrid.remote.coordinator.ExporterSession</code> method), 146
<code>__repr__()</code> (<code>labgrid.driver.ubootdriver.UBOOTDriver</code> method), 130	<code>__repr__()</code> (<code>labgrid.remote.coordinator.RemoteSession</code> method), 145
<code>__repr__()</code> (<code>labgrid.driver.usbloader.IMXUSBDriver</code> method), 131	<code>__repr__()</code> (<code>labgrid.remote.coordinator.ResourceImport</code> method), 146
<code>__repr__()</code> (<code>labgrid.driver.usbloader.MXSUSBDriver</code> method), 130	<code>__repr__()</code> (<code>labgrid.remote.exporter.EthernetPortExport</code> method), 150
<code>__repr__()</code> (<code>labgrid.driver.usbloader.RKUSBDriver</code> method), 131	<code>__repr__()</code> (<code>labgrid.remote.exporter.GPIOGenericExport</code> method), 151
<code>__repr__()</code> (<code>labgrid.driver.usbloader.UUUDriver</code> method), 132	<code>__repr__()</code> (<code>labgrid.remote.exporter.LXAIOBusNodeExport</code> method), 152
<code>__repr__()</code> (<code>labgrid.driver.usbsdmuxdriver.USBSDMuxDriver</code> method), 132	<code>__repr__()</code> (<code>labgrid.remote.exporter.NetworkServiceExport</code> method), 151
<code>__repr__()</code> (<code>labgrid.driver.usbsdwiredriver.USBSDWireDriver</code> method), 132	<code>__repr__()</code> (<code>labgrid.remote.exporter.ResourceExport</code> method), 147
<code>__repr__()</code> (<code>labgrid.driver.usbstoragedriver.NetworkUSBStorageDriver</code> method), 133	<code>__repr__()</code> (<code>labgrid.remote.exporter.SerialPortExport</code> method), 147
<code>__repr__()</code> (<code>labgrid.driver.usbstoragedriver.USBStorageDriver</code> method), 133	<code>__repr__()</code> (<code>labgrid.remote.exporter.SiSPMPowerPortExport</code> method), 149
<code>__repr__()</code> (<code>labgrid.driver.usbtmcdriver.USBTMCDriver</code> method), 134	<code>__repr__()</code> (<code>labgrid.remote.exporter.USBDeditecRelaisExport</code> method), 150
<code>__repr__()</code> (<code>labgrid.driver.usbviedriver.USBVideoDriver</code> method), 135	<code>__repr__()</code> (<code>labgrid.remote.exporter.USBEthernetExport</code> method), 148
<code>__repr__()</code> (<code>labgrid.driver.xenadriver.XenaDriver</code> method), 135	<code>__repr__()</code> (<code>labgrid.remote.exporter.USBGenericExport</code> method), 148
<code>__repr__()</code> (<code>labgrid.environment.Environment</code> method), 196	<code>__repr__()</code> (<code>labgrid.remote.exporter.USBPowerPortExport</code> method), 150
<code>__repr__()</code> (<code>labgrid.exceptions.InvalidConfigError</code> method), 197	<code>__repr__()</code> (<code>labgrid.remote.exporter.USBSDMuxExport</code> method), 149
<code>__repr__()</code> (<code>labgrid.exceptions.NoConfigFoundError</code> method), 197	<code>__repr__()</code> (<code>labgrid.remote.exporter.USBSDWireExport</code> method), 149
<code>__repr__()</code> (<code>labgrid.exceptions.NoDriverFoundError</code> method), 197	<code>__repr__()</code> (<code>labgrid.remote.exporter.USBSigrokExport</code> method), 148

<code>__repr__()</code> (<i>labgrid.remote.scheduler.TagSet</i> method), 152	<code>__repr__()</code> (<i>labgrid.resource.remote.NetworkDeditecRelais8</i> method), 168
<code>__repr__()</code> (<i>labgrid.resource.base.EthernetInterface</i> method), 153	<code>__repr__()</code> (<i>labgrid.resource.remote.NetworkIMXUSBLoader</i> method), 164
<code>__repr__()</code> (<i>labgrid.resource.base.EthernetPort</i> method), 154	<code>__repr__()</code> (<i>labgrid.resource.remote.NetworkLXAIOBusNode</i> method), 168
<code>__repr__()</code> (<i>labgrid.resource.base.SerialPort</i> method), 153	<code>__repr__()</code> (<i>labgrid.resource.remote.NetworkLXAIOBusPIO</i> method), 169
<code>__repr__()</code> (<i>labgrid.resource.base.SysfsGPIO</i> method), 154	<code>__repr__()</code> (<i>labgrid.resource.remote.NetworkMXSUSBLoader</i> method), 164
<code>__repr__()</code> (<i>labgrid.resource.common.ManagedResource</i> method), 155	<code>__repr__()</code> (<i>labgrid.resource.remote.NetworkRKUSBLoader</i> method), 165
<code>__repr__()</code> (<i>labgrid.resource.common.NetworkResource</i> method), 155	<code>__repr__()</code> (<i>labgrid.resource.remote.NetworkSiSPMPowerPort</i> method), 167
<code>__repr__()</code> (<i>labgrid.resource.common.Resource</i> method), 154	<code>__repr__()</code> (<i>labgrid.resource.remote.NetworkSigrokUSBDevice</i> method), 165
<code>__repr__()</code> (<i>labgrid.resource.common.ResourceManager</i> method), 155	<code>__repr__()</code> (<i>labgrid.resource.remote.NetworkSigrokUSBSerialDevice</i> method), 165
<code>__repr__()</code> (<i>labgrid.resource.docker.DockerDaemon</i> method), 157	<code>__repr__()</code> (<i>labgrid.resource.remote.NetworkSysfsGPIO</i> method), 168
<code>__repr__()</code> (<i>labgrid.resource.docker.DockerManager</i> method), 156	<code>__repr__()</code> (<i>labgrid.resource.remote.NetworkUSBMassStorage</i> method), 166
<code>__repr__()</code> (<i>labgrid.resource.ethernetport.EthernetPortManager</i> method), 158	<code>__repr__()</code> (<i>labgrid.resource.remote.NetworkUSBPowerPort</i> method), 167
<code>__repr__()</code> (<i>labgrid.resource.ethernetport.SNMPEthernetPort</i> method), 159	<code>__repr__()</code> (<i>labgrid.resource.remote.NetworkUSBSDMuxDevice</i> method), 166
<code>__repr__()</code> (<i>labgrid.resource.ethernetport.SNMPSwitch</i> method), 158	<code>__repr__()</code> (<i>labgrid.resource.remote.NetworkUSBSDWireDevice</i> method), 166
<code>__repr__()</code> (<i>labgrid.resource.flashrom.Flashrom</i> method), 159	<code>__repr__()</code> (<i>labgrid.resource.remote.NetworkUSBTMC</i> method), 167
<code>__repr__()</code> (<i>labgrid.resource.flashrom.NetworkFlashrom</i> method), 160	<code>__repr__()</code> (<i>labgrid.resource.remote.NetworkUSBVideo</i> method), 167
<code>__repr__()</code> (<i>labgrid.resource.lxaiobus.LXAIOBusNode</i> method), 160	<code>__repr__()</code> (<i>labgrid.resource.remote.RemotePlace</i> method), 163
<code>__repr__()</code> (<i>labgrid.resource.lxaiobus.LXAIOBusNodeManager</i> method), 160	<code>__repr__()</code> (<i>labgrid.resource.remote.RemotePlaceManager</i> method), 163
<code>__repr__()</code> (<i>labgrid.resource.lxaiobus.LXAIOBusPIO</i> method), 161	<code>__repr__()</code> (<i>labgrid.resource.remote.RemoteUSBResource</i> method), 164
<code>__repr__()</code> (<i>labgrid.resource.modbus.ModbusTCPCoil</i> method), 161	<code>__repr__()</code> (<i>labgrid.resource.serialport.NetworkSerialPort</i> method), 169
<code>__repr__()</code> (<i>labgrid.resource.networkservice.NetworkService</i> method), 161	<code>__repr__()</code> (<i>labgrid.resource.serialport.RawSerialPort</i> method), 169
<code>__repr__()</code> (<i>labgrid.resource.onewireport.OneWirePIO</i> method), 162	<code>__repr__()</code> (<i>labgrid.resource.sigrok.SigrokDevice</i> method), 170
<code>__repr__()</code> (<i>labgrid.resource.power.NetworkPowerPort</i> method), 162	<code>__repr__()</code> (<i>labgrid.resource.udev.AlteraUSBBlander</i> method), 173
<code>__repr__()</code> (<i>labgrid.resource.power.PDUDaemonPort</i> method), 162	<code>__repr__()</code> (<i>labgrid.resource.udev.AndroidFastboot</i> method), 173
<code>__repr__()</code> (<i>labgrid.resource.pyvisa.PyVISADevice</i> method), 163	<code>__repr__()</code> (<i>labgrid.resource.udev.DeditecRelais8</i> method), 176
<code>__repr__()</code> (<i>labgrid.resource.remote.NetworkAlteraUSBBlander</i> method), 165	<code>__repr__()</code> (<i>labgrid.resource.udev.IMXUSBLoader</i> method), 172
<code>__repr__()</code> (<i>labgrid.resource.remote.NetworkAndroidFastboot</i> method), 164	<code>__repr__()</code> (<i>labgrid.resource.udev.MXSUSBLoader</i> method), 172

<code>__repr__()</code> (<i>labgrid.resource.udev.RKUSBLoader</i> method), 172	<code>__repr__()</code> (<i>labgrid.util.qmp.QMPMonitor</i> method), 188
<code>__repr__()</code> (<i>labgrid.resource.udev.SiSPMPowerPort</i> method), 175	<code>__repr__()</code> (<i>labgrid.util.ssh.ForwardError</i> method), 190
<code>__repr__()</code> (<i>labgrid.resource.udev.SigrokUSBDevice</i> method), 174	<code>__repr__()</code> (<i>labgrid.util.ssh.SSHConnection</i> method), 190
<code>__repr__()</code> (<i>labgrid.resource.udev.SigrokUSBSerialDevice</i> method), 174	<code>__repr__()</code> (<i>labgrid.util.timeout.Timeout</i> method), 191
<code>__repr__()</code> (<i>labgrid.resource.udev.USBEthernetInterface</i> method), 173	<code>__setitem__()</code> (<i>labgrid.step.StepEvent</i> method), 199
<code>__repr__()</code> (<i>labgrid.resource.udev.USBMassStorage</i> method), 172	<code>__str__()</code> (<i>labgrid.remote.common.ResourceMatch</i> method), 143
<code>__repr__()</code> (<i>labgrid.resource.udev.USBPowerPort</i> method), 175	<code>__str__()</code> (<i>labgrid.step.Step</i> method), 200
<code>__repr__()</code> (<i>labgrid.resource.udev.USBResource</i> method), 171	<code>__str__()</code> (<i>labgrid.step.StepEvent</i> method), 199
<code>__repr__()</code> (<i>labgrid.resource.udev.USBSDMuxDevice</i> method), 175	<code>__weakref__</code> (<i>labgrid.autoinstall.main.Manager</i> attribute), 101
<code>__repr__()</code> (<i>labgrid.resource.udev.USBSDWireDevice</i> method), 174	<code>__weakref__</code> (<i>labgrid.binding.BindingError</i> attribute), 192
<code>__repr__()</code> (<i>labgrid.resource.udev.USBSerialPort</i> method), 171	<code>__weakref__</code> (<i>labgrid.binding.BindingMixin</i> attribute), 193
<code>__repr__()</code> (<i>labgrid.resource.udev.USBTMC</i> method), 176	<code>__weakref__</code> (<i>labgrid.binding.BindingMixin.NamedBinding</i> attribute), 193
<code>__repr__()</code> (<i>labgrid.resource.udev.USBVideo</i> method), 176	<code>__weakref__</code> (<i>labgrid.binding.StateError</i> attribute), 192
<code>__repr__()</code> (<i>labgrid.resource.udev.UdevManager</i> method), 170	<code>__weakref__</code> (<i>labgrid.config.Config</i> attribute), 195
<code>__repr__()</code> (<i>labgrid.resource.xenamanager.XenaManager</i> method), 176	<code>__weakref__</code> (<i>labgrid.consoleloggingreporter.ConsoleLoggingReporter</i> attribute), 196
<code>__repr__()</code> (<i>labgrid.resource.ykushpowerport.YKUSHPowerPort</i> method), 177	<code>__weakref__</code> (<i>labgrid.driver.commandmixin.CommandMixin</i> attribute), 106
<code>__repr__()</code> (<i>labgrid.step.Step</i> method), 199	<code>__weakref__</code> (<i>labgrid.driver.consoleexpectmixin.ConsoleExpectMixin</i> attribute), 107
<code>__repr__()</code> (<i>labgrid.strategy.bareboxstrategy.BareboxStrategy</i> method), 177	<code>__weakref__</code> (<i>labgrid.driver.exception.CleanUpError</i> attribute), 109
<code>__repr__()</code> (<i>labgrid.strategy.common.Strategy</i> method), 178	<code>__weakref__</code> (<i>labgrid.driver.exception.ExecutionError</i> attribute), 109
<code>__repr__()</code> (<i>labgrid.strategy.common.StrategyError</i> method), 178	<code>__weakref__</code> (<i>labgrid.environment.Environment</i> attribute), 197
<code>__repr__()</code> (<i>labgrid.strategy.dockerstrategy.DockerStrategy</i> method), 179	<code>__weakref__</code> (<i>labgrid.exceptions.InvalidConfigError</i> attribute), 197
<code>__repr__()</code> (<i>labgrid.strategy.shellstrategy.ShellStrategy</i> method), 180	<code>__weakref__</code> (<i>labgrid.exceptions.NoConfigFoundError</i> attribute), 197
<code>__repr__()</code> (<i>labgrid.strategy.ubootstrategy.UBootStrategy</i> method), 181	<code>__weakref__</code> (<i>labgrid.exceptions.NoSupplierFoundError</i> attribute), 197
<code>__repr__()</code> (<i>labgrid.target.Target</i> method), 202	<code>__weakref__</code> (<i>labgrid.exceptions.RegistrationError</i> attribute), 198
<code>__repr__()</code> (<i>labgrid.util.exceptions.NoValidDriverError</i> method), 184	<code>__weakref__</code> (<i>labgrid.factory.TargetFactory</i> attribute), 198
<code>__repr__()</code> (<i>labgrid.util.helper.ProcessWrapper</i> method), 186	<code>__weakref__</code> (<i>labgrid.protocol.bootstrapprotocol.BootstrapProtocol</i> attribute), 135
<code>__repr__()</code> (<i>labgrid.util.managedfile.ManagedFile</i> method), 187	<code>__weakref__</code> (<i>labgrid.protocol.commandprotocol.CommandProtocol</i> attribute), 136
<code>__repr__()</code> (<i>labgrid.util.qmp.QMPError</i> method), 188	<code>__weakref__</code> (<i>labgrid.protocol.consoleprotocol.ConsoleProtocol</i> attribute), 137
	<code>__weakref__</code> (<i>labgrid.protocol.consoleprotocol.ConsoleProtocol.Client</i> attribute), 136

- __weakref__ (labgrid.protocol.digitaloutputprotocol.DigitalOutputProtocol attribute), 137
 - __weakref__ (labgrid.protocol.filesystemprotocol.FileSystemProtocol attribute), 137
 - __weakref__ (labgrid.protocol.filetransferprotocol.FileTransferProtocol attribute), 138
 - __weakref__ (labgrid.protocol.infoprotocol.InfoProtocol attribute), 138
 - __weakref__ (labgrid.protocol.linuxbootprotocol.LinuxBootProtocol attribute), 138
 - __weakref__ (labgrid.protocol.mmioprotocol.MMIOProtocol attribute), 139
 - __weakref__ (labgrid.protocol.powerprotocol.PowerProtocol attribute), 139
 - __weakref__ (labgrid.protocol.resetprotocol.ResetProtocol attribute), 139
 - __weakref__ (labgrid.provider.fileprovider.FileProvider attribute), 140
 - __weakref__ (labgrid.pytestplugin.reporter.StepReporter attribute), 141
 - __weakref__ (labgrid.remote.client.Error attribute), 141
 - __weakref__ (labgrid.remote.common.Place attribute), 144
 - __weakref__ (labgrid.remote.common.Reservation attribute), 144
 - __weakref__ (labgrid.remote.common.ResourceEntry attribute), 142
 - __weakref__ (labgrid.remote.common.ResourceMatch attribute), 143
 - __weakref__ (labgrid.remote.config.ResourceConfig attribute), 145
 - __weakref__ (labgrid.remote.coordinator.RemoteSession attribute), 145
 - __weakref__ (labgrid.remote.exporter.ExporterError attribute), 146
 - __weakref__ (labgrid.remote.scheduler.TagSet attribute), 152
 - __weakref__ (labgrid.resource.common.ResourceManager attribute), 155
 - __weakref__ (labgrid.resource.docker.DockerConstants attribute), 156
 - __weakref__ (labgrid.resource.ethernetport.SNMPSwitch attribute), 158
 - __weakref__ (labgrid.resource.suggest.Suggester attribute), 170
 - __weakref__ (labgrid.step.Step attribute), 200
 - __weakref__ (labgrid.step.StepEvent attribute), 199
 - __weakref__ (labgrid.step.Steps attribute), 199
 - __weakref__ (labgrid.stepreporter.StepReporter attribute), 200
 - __weakref__ (labgrid.strategy.common.StrategyError attribute), 178
 - __weakref__ (labgrid.target.Target attribute), 202
 - __weakref__ (labgrid.util.agent.Agent attribute), 182
 - __weakref__ (labgrid.util.agents.sysfsgpio.GpioDigitalOutput attribute), 182
 - __weakref__ (labgrid.util.agentwrapper.AgentError attribute), 183
 - __weakref__ (labgrid.util.agentwrapper.AgentException attribute), 183
 - __weakref__ (labgrid.util.agentwrapper.AgentWrapper attribute), 183
 - __weakref__ (labgrid.util.agentwrapper.MethodProxy attribute), 183
 - __weakref__ (labgrid.util.agentwrapper.ModuleProxy attribute), 183
 - __weakref__ (labgrid.util.exceptions.NoValidDriverError attribute), 184
 - __weakref__ (labgrid.util.helper.ProcessWrapper attribute), 186
 - __weakref__ (labgrid.util.managedfile.ManagedFile attribute), 187
 - __weakref__ (labgrid.util.qmp.QMPError attribute), 188
 - __weakref__ (labgrid.util.qmp.QMPMonitor attribute), 188
 - __weakref__ (labgrid.util.ssh.ForwardError attribute), 190
 - __weakref__ (labgrid.util.ssh.SSHConnection attribute), 190
 - __weakref__ (labgrid.util.timeout.Timeout attribute), 191
- ## A
- accessible (labgrid.strategy.dockerstrategy.Status attribute), 179
 - acquire() (labgrid.remote.common.ResourceEntry method), 142
 - acquire() (labgrid.remote.exporter.ResourceExport method), 147
 - acquired (labgrid.remote.common.ReservationState attribute), 144
 - acquired() (labgrid.remote.common.ResourceEntry property), 142
 - Action (class in labgrid.remote.coordinator), 145
 - activate() (labgrid.target.Target method), 201
 - active (labgrid.binding.BindingState attribute), 192
 - ADD (labgrid.remote.coordinator.Action attribute), 145
 - add_port_forward() (labgrid.util.ssh.SSHConnection method), 189
 - age() (labgrid.step.StepEvent property), 199
 - Agent (class in labgrid.util.agent), 182
 - AgentError, 183
 - AgentException, 183
 - AgentWrapper (class in labgrid.util.agentwrapper), 183

- allocated (*labgrid.remote.common.ReservationState attribute*), 144
- AlteraUSBBlaster (*class in labgrid.resource.udev*), 173
- analyze() (*labgrid.driver.sigrokdriver.SigrokDriver method*), 126
- AndroidFastboot (*class in labgrid.resource.udev*), 172
- AndroidFastbootDriver (*class in labgrid.driver.fastbootdriver*), 111
- args() (*labgrid.remote.common.ResourceEntry property*), 142
- asdict() (*labgrid.remote.common.Place method*), 143
- asdict() (*labgrid.remote.common.Reservation method*), 144
- asdict() (*labgrid.remote.common.ResourceEntry method*), 142
- atomic_replace() (*in module labgrid.util.atomic*), 184
- avail() (*labgrid.remote.common.ResourceEntry property*), 142
- avail() (*labgrid.resource.udev.USBMassStorage property*), 171
- avail() (*labgrid.resource.udev.USBSDMuxDevice property*), 175
- avail() (*labgrid.resource.udev.USBSDWireDevice property*), 174
- await_boot() (*labgrid.driver.bareboxdriver.BareboxDriver method*), 104
- await_boot() (*labgrid.driver.ubootdriver.UBootDriver method*), 130
- await_boot() (*labgrid.protocol.linuxbootprotocol.LinuxBootProtocol method*), 138
- await_resources() (*labgrid.target.Target method*), 201
- ## B
- b2s() (*in module labgrid.util.agent*), 182
- b2s() (*in module labgrid.util.agentwrapper*), 183
- barebox (*labgrid.strategy.bareboxstrategy.Status attribute*), 177
- BareboxDriver (*class in labgrid.driver.bareboxdriver*), 104
- BareboxStrategy (*class in labgrid.strategy.bareboxstrategy*), 177
- bind() (*labgrid.target.Target method*), 201
- bind_driver() (*labgrid.target.Target method*), 201
- bind_resource() (*labgrid.target.Target method*), 201
- BindingError, 192
- BindingMixin (*class in labgrid.binding*), 192
- BindingMixin.NamedBinding (*class in labgrid.binding*), 193
- bindings (*labgrid.binding.BindingMixin attribute*), 192
- bindings (*labgrid.driver.bareboxdriver.BareboxDriver attribute*), 104
- bindings (*labgrid.driver.deditecrelaisdriver.DeditecRelaisDriver attribute*), 107
- bindings (*labgrid.driver.dockerdriver.DockerDriver attribute*), 108
- bindings (*labgrid.driver.fastbootdriver.AndroidFastbootDriver attribute*), 111
- bindings (*labgrid.driver.filedigitaloutput.FileDigitalOutputDriver attribute*), 112
- bindings (*labgrid.driver.flashromdriver.FlashromDriver attribute*), 112
- bindings (*labgrid.driver.gpiodriver.GpioDigitalOutputDriver attribute*), 113
- bindings (*labgrid.driver.lxaibusdriver.LXAIOBusPIODriver attribute*), 113
- bindings (*labgrid.driver.modbusdriver.ModbusCoilDriver attribute*), 114
- bindings (*labgrid.driver.onewiredriver.OneWirePIODriver attribute*), 114
- bindings (*labgrid.driver.openocddriver.OpenOCDDriver attribute*), 115
- bindings (*labgrid.driver.powerdriver.DigitalOutputPowerDriver attribute*), 117
- bindings (*labgrid.driver.powerdriver.NetworkPowerDriver attribute*), 117
- bindings (*labgrid.driver.powerdriver.PDUDaemonDriver attribute*), 119
- bindings (*labgrid.driver.powerdriver.SiSPMPowerDriver attribute*), 116
- bindings (*labgrid.driver.powerdriver.USBPowerDriver attribute*), 118
- bindings (*labgrid.driver.powerdriver.YKUSHPowerDriver attribute*), 118
- bindings (*labgrid.driver.pyvisadriver.PyVISADriver attribute*), 119
- bindings (*labgrid.driver.quartushpsdriver.QuartusHPSDriver attribute*), 121
- bindings (*labgrid.driver.resetdriver.DigitalOutputResetDriver attribute*), 121
- bindings (*labgrid.driver.serialdigitaloutput.SerialPortDigitalOutputDriver attribute*), 122
- bindings (*labgrid.driver.serialdriver.SerialDriver attribute*), 122
- bindings (*labgrid.driver.shelldriver.ShellDriver attribute*), 123
- bindings (*labgrid.driver.sigrokdriver.SigrokDriver attribute*), 126
- bindings (*labgrid.driver.sigrokdriver.SigrokPowerDriver attribute*), 126

- `bindings` (`labgrid.driver.sshdriver.SSHDriver` attribute), 128
 - `bindings` (`labgrid.driver.ubootdriver.UBootDriver` attribute), 129
 - `bindings` (`labgrid.driver.usbloader.IMXUSBDriver` attribute), 130
 - `bindings` (`labgrid.driver.usbloader.MXSUSBDriver` attribute), 130
 - `bindings` (`labgrid.driver.usbloader.RKUSBDriver` attribute), 131
 - `bindings` (`labgrid.driver.usbloader.UUUDriver` attribute), 131
 - `bindings` (`labgrid.driver.usbsdmuxdriver.USBSDMuxDriver` attribute), 132
 - `bindings` (`labgrid.driver.usbsdwiredriver.USBSDWireDriver` attribute), 132
 - `bindings` (`labgrid.driver.usbstoragedriver.USBStorageDriver` attribute), 133
 - `bindings` (`labgrid.driver.usbtmcdriver.USBTMCDriver` attribute), 134
 - `bindings` (`labgrid.driver.usbvideodriver.USBVideoDriver` attribute), 134
 - `bindings` (`labgrid.driver.xenadriver.XenaDriver` attribute), 135
 - `bindings` (`labgrid.strategy.bareboxstrategy.BareboxStrategy` attribute), 177
 - `bindings` (`labgrid.strategy.dockerstrategy.DockerStrategy` attribute), 179
 - `bindings` (`labgrid.strategy.shellstrategy.ShellStrategy` attribute), 180
 - `bindings` (`labgrid.strategy.ubootstrategy.UBootStrategy` attribute), 181
 - `BindingState` (class in `labgrid.binding`), 192
 - `BMAPTOOL` (`labgrid.driver.usbstoragedriver.Mode` attribute), 133
 - `boot()` (`labgrid.driver.bareboxdriver.BareboxDriver` method), 105
 - `boot()` (`labgrid.driver.fastbootdriver.AndroidFastbootDriver` method), 111
 - `boot()` (`labgrid.driver.smallubootdriver.SmallUBootDriver` method), 127
 - `boot()` (`labgrid.driver.ubootdriver.UBootDriver` method), 130
 - `boot()` (`labgrid.protocol.linuxbootprotocol.LinuxBootProtocol` method), 138
 - `BootstrapProtocol` (class in `labgrid.protocol.bootstrapprotocol`), 135
 - `bound` (`labgrid.binding.BindingState` attribute), 192
 - `broken()` (`labgrid.remote.exporter.ResourceExport` property), 147
 - `BrokenResourceError`, 147
 - `busnum()` (`labgrid.resource.udev.USBResource` property), 171
- ## C
- `call()` (`labgrid.util.agentwrapper.AgentWrapper` method), 183
 - `capture()` (`labgrid.driver.sigrokdriver.SigrokDriver` method), 126
 - `check_active()` (`labgrid.binding.BindingMixin` class method), 193
 - `check_file()` (in module `labgrid.driver.common`), 106
 - `check_output()` (`labgrid.util.helper.ProcessWrapper` method), 185
 - `Class_from_string()` (`labgrid.factory.TargetFactory` method), 198
 - `Cleanup()` (`labgrid.environment.Environment` method), 196
 - `Cleanup()` (`labgrid.target.Target` method), 202
 - `cleanup()` (`labgrid.util.ssh.SSHConnection` method), 189
 - `CleanUpError`, 109
 - `ClientSession` (class in `labgrid.remote.coordinator`), 146
 - `close()` (`labgrid.driver.externalconsoledriver.ExternalConsoleDriver` method), 109
 - `close()` (`labgrid.driver.fake.FakeConsoleDriver` method), 110
 - `close()` (`labgrid.driver.serialdriver.SerialDriver` method), 123
 - `close()` (`labgrid.util.agentwrapper.AgentWrapper` method), 184
 - `cls()` (`labgrid.remote.common.ResourceEntry` property), 142
 - `ColoredStepReporter` (class in `labgrid.pytestplugin.reporter`), 141
 - `command()` (`labgrid.driver.usbtmcdriver.USBTMCDriver` method), 134
 - `command_prefix()` (`labgrid.resource.common.NetworkResource` property), 155
 - `command_prefix()` (`labgrid.resource.common.Resource` property), 154
 - `CommandMixin` (class in `labgrid.driver.commandmixin`), 105
 - `CommandProtocol` (class in `labgrid.protocol.commandprotocol`), 136
 - `Config` (class in `labgrid.config`), 193
 - `configure()` (`labgrid.autoinstall.main.Manager` method), 101
 - `connect()` (`labgrid.util.ssh.SSHConnection` method), 189
 - `ConsoleExpectMixin` (class in `labgrid.driver.consoleexpectmixin`), 106
 - `ConsoleLoggingReporter` (class in `lab-`

[grid.consoleloggingreporter](#)), 196
[ConsoleProtocol](#) (class in [lab-grid.protocol.consoleprotocol](#)), 136
[ConsoleProtocol.Client](#) (class in [lab-grid.protocol.consoleprotocol](#)), 136
[continue_boot\(\)](#) ([lab-grid.driver.fastbootdriver.AndroidFastbootDriver](#) method), 111
[cycle\(\)](#) ([labgrid.driver.dockerdriver.DockerDriver](#) method), 108
[cycle\(\)](#) ([labgrid.driver.fake.FakePowerDriver](#) method), 111
[cycle\(\)](#) ([labgrid.driver.powerdriver.DigitalOutputPowerDriver](#) method), 118
[cycle\(\)](#) ([labgrid.driver.powerdriver.ExternalPowerDriver](#) method), 117
[cycle\(\)](#) ([labgrid.driver.powerdriver.ManualPowerDriver](#) method), 116
[cycle\(\)](#) ([labgrid.driver.powerdriver.NetworkPowerDriver](#) method), 117
[cycle\(\)](#) ([labgrid.driver.powerdriver.PDUDaemonDriver](#) method), 119
[cycle\(\)](#) ([labgrid.driver.powerdriver.SiSPMPowerDriver](#) method), 116
[cycle\(\)](#) ([labgrid.driver.powerdriver.USBPowerDriver](#) method), 118
[cycle\(\)](#) ([labgrid.driver.powerdriver.YKUSHPowerDriver](#) method), 118
[cycle\(\)](#) ([labgrid.driver.qemudriver.QEMUDriver](#) method), 121
[cycle\(\)](#) ([labgrid.driver.sigrokdriver.SigrokPowerDriver](#) method), 126
[cycle\(\)](#) ([labgrid.protocol.powerprotocol.PowerProtocol](#) method), 139
[DigitalOutputResetDriver](#) (class in [lab-grid.driver.resetdriver](#)), 121
[disable_logging\(\)](#) ([lab-grid.util.helper.ProcessWrapper](#) method), 185
[disable_print\(\)](#) ([lab-grid.util.helper.ProcessWrapper](#) method), 185
[disconnect\(\)](#) ([labgrid.util.ssh.SSHConnection](#) method), 189
[display_name\(\)](#) ([labgrid.binding.BindingMixin](#) property), 192
[docker_daemon_url](#) ([lab-grid.resource.docker.DockerDaemon](#) attribute), 156
[DOCKER_LG_CLEANUP_LABEL](#) ([lab-grid.resource.docker.DockerConstants](#) attribute), 156
[DOCKER_LG_CLEANUP_TYPE_AUTO](#) ([lab-grid.resource.docker.DockerConstants](#) attribute), 156
[DockerConstants](#) (class in [labgrid.resource.docker](#)), 156
[DockerDaemon](#) (class in [labgrid.resource.docker](#)), 156
[DockerDriver](#) (class in [labgrid.driver.dockerdriver](#)), 107
[DockerManager](#) (class in [labgrid.resource.docker](#)), 156
[DockerStrategy](#) (class in [lab-grid.strategy.dockerstrategy](#)), 179
[Driver](#) (class in [labgrid.driver.common](#)), 106
[dump\(\)](#) (in module [labgrid.util.yaml](#)), 191
[Dumper](#) (class in [labgrid.util.yaml](#)), 191
[duration\(\)](#) ([labgrid.step.Step](#) property), 200

D

[DD](#) ([labgrid.driver.usbstoragedriver.Mode](#) attribute), 133
[deactivate\(\)](#) ([labgrid.target.Target](#) method), 201
[deactivate_all_drivers\(\)](#) ([lab-grid.target.Target](#) method), 201
[DeditecRelais8](#) (class in [labgrid.resource.udev](#)), 176
[DeditecRelaisDriver](#) (class in [lab-grid.driver.deditecrelaisdriver](#)), 107
[DEL](#) ([labgrid.remote.coordinator.Action](#) attribute), 145
[depends\(\)](#) ([labgrid.strategy.graphstrategy.GraphStrategy](#) class method), 180
[devnum\(\)](#) ([labgrid.resource.udev.USBResource](#) property), 171
[diff_dict\(\)](#) (in module [labgrid.util.dict](#)), 184
[DigitalOutputPowerDriver](#) (class in [lab-grid.driver.powerdriver](#)), 117
[DigitalOutputProtocol](#) (class in [lab-grid.protocol.digitaloutputprotocol](#)), 137

E

[enable_logging\(\)](#) ([lab-grid.util.helper.ProcessWrapper](#) method), 185
[enable_print\(\)](#) ([lab-grid.util.helper.ProcessWrapper](#) method), 185
[enable_tcp_nodelay\(\)](#) (in module [lab-grid.remote.common](#)), 144
[env\(\)](#) (in module [labgrid.pytestplugin.fixtures](#)), 140
[Environment](#) (class in [labgrid.environment](#)), 196
[erase\(\)](#) ([labgrid.driver.quartushpsdriver.QuartusHPSDriver](#) method), 121
[Error](#), 141
[error](#) ([labgrid.binding.BindingState](#) attribute), 192
[EthernetInterface](#) (class in [lab-grid.resource.base](#)), 153
[EthernetPort](#) (class in [labgrid.resource.base](#)), 153

EthernetPortExport (class in lab- 173
 grid.remote.exporter), 150
 EthernetPortManager (class in lab-
 grid.resource.ethernetport), 158
 EVENT_COLORS_DARK (lab-
 grid.pytestplugin.reporter.ColoredStepReporter
 attribute), 141
 EVENT_COLORS_LIGHT (lab-
 grid.pytestplugin.reporter.ColoredStepReporter
 attribute), 141
 execute() (labgrid.driver.openocddriver.OpenOCDDriver
 method), 115
 execute() (labgrid.util.qmp.QMPMonitor method),
 187
 ExecutionError, 108
 expect() (labgrid.driver.consoleexpectmixin.ConsoleExpectMixin
 method), 107
 expect() (labgrid.protocol.consoleprotocol.ConsoleProtocol
 method), 136
 expired (labgrid.remote.common.ReservationState at-
 tribute), 144
 expired() (labgrid.remote.common.Reservation prop-
 erty), 144
 expired() (labgrid.util.timeout.Timeout property),
 191
 ExporterError, 146
 ExporterSession (class in lab-
 grid.remote.coordinator), 145
 ExternalConsoleDriver (class in lab-
 grid.driver.externalconsoledriver), 109
 ExternalPowerDriver (class in lab-
 grid.driver.powerdriver), 116
 extra() (labgrid.remote.common.ResourceEntry prop-
 erty), 142

F

FakeCommandDriver (class in labgrid.driver.fake),
 110
 FakeConsoleDriver (class in labgrid.driver.fake),
 109
 FakeFileTransferDriver (class in lab-
 grid.driver.fake), 110
 FakePowerDriver (class in labgrid.driver.fake), 111
 FileDigitalOutputDriver (class in lab-
 grid.driver.filedigitaloutput), 112
 FileProvider (class in labgrid.provider.fileprovider),
 139
 FileSystemProtocol (class in lab-
 grid.protocol.filesystemprotocol), 137
 FileTransferProtocol (class in lab-
 grid.protocol.filetransferprotocol), 137
 filter_dict() (in module labgrid.util.dict), 184
 filter_match() (lab-
 grid.resource.udev.AlterUSBBlaster method),

filter_match() (lab-
 grid.resource.udev.AndroidFastboot method),
 172
 filter_match() (lab-
 grid.resource.udev.IMXUSBLoader method),
 172
 filter_match() (lab-
 grid.resource.udev.MXSUSBLoader method),
 172
 filter_match() (lab-
 grid.resource.udev.RKUSBLoader method),
 172
 filter_match() (lab-
 grid.resource.udev.SiSPMPowerPort method),
 175
 filter_match() (lab-
 grid.resource.udev.USBResource method),
 171
 find_abs_path() (lab-
 grid.strategy.graphstrategy.GraphStrategy
 method), 180
 find_any_role_with_place() (in module lab-
 grid.remote.client), 142
 find_dict() (in module labgrid.util.dict), 184
 find_rel_path() (lab-
 grid.strategy.graphstrategy.GraphStrategy
 method), 180
 find_role_by_place() (in module lab-
 grid.remote.client), 142
 flash() (labgrid.driver.fastbootdriver.AndroidFastbootDriver
 method), 111
 flash() (labgrid.driver.quartushpsdriver.QuartusHPSDriver
 method), 121
 Flashrom (class in labgrid.resource.flashrom), 159
 FlashromDriver (class in lab-
 grid.driver.flashromdriver), 112
 flat_dict() (in module labgrid.util.dict), 184
 force() (labgrid.strategy.common.Strategy method),
 178
 force() (labgrid.strategy.shellstrategy.ShellStrategy
 method), 180
 ForwardError, 190
 fromstr() (labgrid.remote.common.ResourceMatch
 class method), 142

G

gen_marker() (in module labgrid.util.marker), 187
 get() (labgrid.driver.deditecrelaisdriver.DeditecRelaisDriver
 method), 107
 get() (labgrid.driver.fake.FakeFileTransferDriver
 method), 110
 get() (labgrid.driver.filedigitaloutput.FileDigitalOutputDriver
 method), 112

[get \(\) \(labgrid.driver.gpiodriver.GpioDigitalOutputDriver method\), 113](#)
[get \(\) \(labgrid.driver.lxaibusdriver.LXAIOBusPIODriver method\), 114](#)
[get \(\) \(labgrid.driver.modbusdriver.ModbusCoilDriver method\), 114](#)
[get \(\) \(labgrid.driver.onewiredriver.OneWirePIODriver method\), 115](#)
[get \(\) \(labgrid.driver.powerdriver.DigitalOutputPowerDriver method\), 118](#)
[get \(\) \(labgrid.driver.powerdriver.NetworkPowerDriver method\), 117](#)
[get \(\) \(labgrid.driver.powerdriver.PDUDaemonDriver method\), 119](#)
[get \(\) \(labgrid.driver.powerdriver.SiSPMPowerDriver method\), 116](#)
[get \(\) \(labgrid.driver.powerdriver.USBPowerDriver method\), 118](#)
[get \(\) \(labgrid.driver.powerdriver.YKUSHPowerDriver method\), 118](#)
[get \(\) \(labgrid.driver.serialdigitaloutput.SerialPortDigitalOutputDriver method\), 122](#)
[get \(\) \(labgrid.driver.shelldriver.ShellDriver method\), 124](#)
[get \(\) \(labgrid.driver.sigrokdriver.SigrokPowerDriver method\), 126](#)
[get \(\) \(labgrid.driver.sshdriver.SSHDriver method\), 128](#)
[get \(\) \(labgrid.protocol.digitaloutputprotocol.DigitalOutputProtocol method\), 137](#)
[get \(\) \(labgrid.protocol.filetransferprotocol.FileTransferProtocol method\), 137](#)
[get \(\) \(labgrid.provider.fileprovider.FileProvider method\), 139](#)
[get \(\) \(labgrid.provider.mediafileprovider.MediaFileProvider method\), 140](#)
[get \(\) \(labgrid.resource.common.ResourceManager class method\), 155](#)
[get \(\) \(labgrid.util.agents.sysfsgpio.GpioDigitalOutput method\), 182](#)
[get_active_driver \(\) \(labgrid.target.Target method\), 201](#)
[get_bool \(\) \(labgrid.driver.usbtmcdriver.USBTMCDriver method\), 134](#)
[get_bytes \(\) \(labgrid.driver.shelldriver.ShellDriver method\), 124](#)
[get_caps \(\) \(labgrid.driver.usbviedriver.USBVideoDriver method\), 134](#)
[get_channel_info \(\) \(in module labgrid.driver.usbtmc.keysight_dsox2000\), 103](#)
[get_channel_info \(\) \(in module labgrid.driver.usbtmc.tektronix_tds2000\), 104](#)
[get_channel_info \(\) \(labgrid.driver.usbtmcdriver.USBTMCDriver method\), 134](#)
[get_channel_values \(\) \(in module labgrid.driver.usbtmc.keysight_dsox2000\), 103](#)
[get_channel_values \(\) \(in module labgrid.driver.usbtmc.tektronix_tds2000\), 104](#)
[get_channel_values \(\) \(labgrid.driver.usbtmcdriver.USBTMCDriver method\), 134](#)
[get_console_matches \(\) \(labgrid.protocol.consoleprotocol.ConsoleProtocol.Client method\), 136](#)
[get_current \(\) \(labgrid.step.Steps method\), 199](#)
[get_decimal \(\) \(labgrid.driver.usbtmcdriver.USBTMCDriver method\), 134](#)
[get_driver \(\) \(labgrid.target.Target method\), 201](#)
[get_features \(\) \(labgrid.config.Config method\), 195](#)
[get_features \(\) \(labgrid.environment.Environment method\), 196](#)
[get_file \(\) \(labgrid.util.ssh.SSHConnection method\), 188](#)
[get_free_port \(\) \(in module labgrid.util.helper\), 185](#)
[get_hash \(\) \(labgrid.util.managedfile.ManagedFile method\), 186](#)
[get_hostname \(\) \(labgrid.protocol.infoprotocol.InfoProtocol method\), 138](#)
[get_image_path \(\) \(labgrid.config.Config method\), 194](#)
[get_images \(\) \(labgrid.config.Config method\), 195](#)
[get_imports \(\) \(labgrid.config.Config method\), 195](#)
[get_int \(\) \(labgrid.driver.usbtmcdriver.USBTMCDriver method\), 134](#)
[get_ip \(\) \(labgrid.protocol.infoprotocol.InfoProtocol method\), 138](#)
[get_logfile \(\) \(labgrid.consoleloggingreporter.ConsoleLoggingReporter method\), 196](#)
[get_managed_parent \(\) \(labgrid.resource.common.ManagedResource method\), 156](#)
[get_managed_parent \(\) \(labgrid.resource.common.Resource method\), 154](#)
[get_new \(\) \(labgrid.step.Steps method\), 199](#)
[get_option \(\) \(labgrid.config.Config method\), 194](#)
[get_path \(\) \(labgrid.config.Config method\), 194](#)
[get_paths \(\) \(labgrid.config.Config method\), 195](#)
[get_pipeline \(\) \(labgrid.driver.usbviedriver.USBVideoDriver method\), 134](#)
[get_prefix \(\) \(labgrid.util.ssh.SSHConnection method\), 188](#)

- [get_priority\(\)](#) (*labgrid.driver.common.Driver method*), 106
[get_remote_path\(\)](#) (*labgrid.util.managedfile.ManagedFile method*), 186
[get_resource\(\)](#) (*labgrid.target.Target method*), 201
[get_resources\(\)](#) (*labgrid.remote.coordinator.ExporterSession method*), 146
[get_screenshot\(\)](#) (*labgrid.driver.usbtmcdriver.USBTMCDriver method*), 134
[get_screenshot_png\(\)](#) (*in module labgrid.driver.usbtmc.keysight_dsox2000*), 103
[get_screenshot_tiff\(\)](#) (*in module labgrid.driver.usbtmc.tektronix_tds2000*), 104
[get_service_status\(\)](#) (*labgrid.protocol.infoprotocol.InfoProtocol method*), 138
[get_session\(\)](#) (*labgrid.driver.pyvisadriver.PyVISADriver method*), 119
[get_session\(\)](#) (*labgrid.driver.xenadriver.XenaDriver method*), 135
[get_size\(\)](#) (*labgrid.driver.usbstoragedriver.USBStorageDriver method*), 133
[get_state\(\)](#) (*in module labgrid.driver.power.gude24*), 102
[get_status\(\)](#) (*labgrid.driver.bareboxdriver.BareboxDriver method*), 104
[get_status\(\)](#) (*labgrid.driver.fake.FakeCommandDriver method*), 110
[get_status\(\)](#) (*labgrid.driver.shelldriver.ShellDriver method*), 124
[get_status\(\)](#) (*labgrid.driver.sshdriver.SSHDriver method*), 128
[get_status\(\)](#) (*labgrid.driver.ubootdriver.UBootDriver method*), 129
[get_status\(\)](#) (*labgrid.protocol.commandprotocol.CommandProtocol method*), 136
[get_str\(\)](#) (*labgrid.driver.usbtmcdriver.USBTMCDriver method*), 134
[get_target\(\)](#) (*labgrid.environment.Environment method*), 196
[get_target_features\(\)](#) (*labgrid.environment.Environment method*), 196
[get_target_option\(\)](#) (*labgrid.config.Config method*), 194
[get_targets\(\)](#) (*labgrid.config.Config method*), 195
[get_tool\(\)](#) (*labgrid.config.Config method*), 194
[get_user\(\)](#) (*in module labgrid.util.helper*), 185
[getmatch\(\)](#) (*labgrid.remote.common.Place method*), 143
[getvar\(\)](#) (*labgrid.driver.fastbootdriver.AndroidFastbootDriver method*), 111
[gone](#) (*labgrid.strategy.dockerstrategy.Status attribute*), 179
[GpioDigitalOutput](#) (*class in labgrid.util.agents.sysfsgpio*), 182
[GpioDigitalOutputDriver](#) (*class in labgrid.driver.gpiodriver*), 113
[GPIOGenericExport](#) (*class in labgrid.remote.exporter*), 151
[graph\(\)](#) (*labgrid.strategy.graphstrategy.GraphStrategy property*), 180
[GraphStrategy](#) (*class in labgrid.strategy.graphstrategy*), 179
[GraphStrategyError](#), 179
[GraphStrategyRuntimeError](#), 179

H

[handle_error\(\)](#) (*in module labgrid.util.agent*), 182
[handle_get\(\)](#) (*in module labgrid.util.agents.sysfsgpio*), 182
[handle_neg\(\)](#) (*in module labgrid.util.agents.dummy*), 181
[handle_set\(\)](#) (*in module labgrid.util.agents.sysfsgpio*), 182
[handle_test\(\)](#) (*in module labgrid.util.agent*), 182
[handle_usbtmc\(\)](#) (*in module labgrid.util.agent*), 182
[Handler](#) (*class in labgrid.autoinstall.main*), 101
[hasmatch\(\)](#) (*labgrid.remote.common.Place method*), 143

I

[identify\(\)](#) (*labgrid.driver.usbtmcdriver.USBTMCDriver method*), 134
[idle](#) (*labgrid.binding.BindingState attribute*), 192
[if_state\(\)](#) (*labgrid.resource.udev.USBEthernetInterface property*), 173
[IMXUSBDriver](#) (*class in labgrid.driver.usbloader*), 130
[IMXUSBLoader](#) (*class in labgrid.resource.udev*), 172
[InfoProtocol](#) (*class in labgrid.protocol.infoprotocol*), 138
[instance](#) (*labgrid.consoleloggingreporter.ConsoleLoggingReporter attribute*), 196
[instance](#) (*labgrid.stepreporter.StepReporter attribute*), 200
[instances](#) (*labgrid.resource.common.ResourceManager attribute*), 155
[interact\(\)](#) (*labgrid.driver.sshdriver.SSHDriver method*), 128

[interact\(\)](#) (*labgrid.target.Target method*), 200
[invalid](#) (*labgrid.remote.common.ReservationState attribute*), 144
[invalidate\(\)](#) (*labgrid.strategy.graphstrategy.GraphStrategy method*), 179
[InvalidConfigError](#), 197
[InvalidGraphStrategyError](#), 179
[is_active\(\)](#) (*labgrid.step.Step property*), 200
[is_done\(\)](#) (*labgrid.step.Step property*), 200
[isconnected\(\)](#) (*labgrid.util.ssh.SSHConnection method*), 189
[ismatch\(\)](#) (*labgrid.remote.common.ResourceMatch method*), 143

J

[join\(\)](#) (*labgrid.autoinstall.main.Manager method*), 101

K

[key\(\)](#) (*labgrid.remote.coordinator.RemoteSession property*), 145

L

[labgrid](#) (*module*), 101
[labgrid.autoinstall](#) (*module*), 101
[labgrid.autoinstall.main](#) (*module*), 101
[labgrid.binding](#) (*module*), 191
[labgrid.config](#) (*module*), 193
[labgrid.consoleloggingreporter](#) (*module*), 196
[labgrid.driver](#) (*module*), 102
[labgrid.driver.bareboxdriver](#) (*module*), 104
[labgrid.driver.commandmixin](#) (*module*), 105
[labgrid.driver.common](#) (*module*), 106
[labgrid.driver.consoleexpectmixin](#) (*module*), 106
[labgrid.driver.deditecrelaisdriver](#) (*module*), 107
[labgrid.driver.dockerdriver](#) (*module*), 107
[labgrid.driver.exception](#) (*module*), 108
[labgrid.driver.externalconsoledriver](#) (*module*), 109
[labgrid.driver.fake](#) (*module*), 109
[labgrid.driver.fastbootdriver](#) (*module*), 111
[labgrid.driver.filedigitaloutput](#) (*module*), 112
[labgrid.driver.flashromdriver](#) (*module*), 112
[labgrid.driver.gpiodriver](#) (*module*), 113
[labgrid.driver.lxaibusdriver](#) (*module*), 113
[labgrid.driver.modbusdriver](#) (*module*), 114

[labgrid.driver.onewiredriver](#) (*module*), 114
[labgrid.driver.openocddriver](#) (*module*), 115
[labgrid.driver.power](#) (*module*), 102
[labgrid.driver.power.apc](#) (*module*), 102
[labgrid.driver.power.digipower](#) (*module*), 102
[labgrid.driver.power.gude](#) (*module*), 102
[labgrid.driver.power.gude24](#) (*module*), 102
[labgrid.driver.power.gude8031](#) (*module*), 102
[labgrid.driver.power.gude8316](#) (*module*), 103
[labgrid.driver.power.netio](#) (*module*), 103
[labgrid.driver.power.netio_kshell](#) (*module*), 103
[labgrid.driver.power.sentry](#) (*module*), 103
[labgrid.driver.power.simplerest](#) (*module*), 103
[labgrid.driver.powerdriver](#) (*module*), 115
[labgrid.driver.pyvisadriver](#) (*module*), 119
[labgrid.driver.qemudriver](#) (*module*), 120
[labgrid.driver.quartushpsdriver](#) (*module*), 121
[labgrid.driver.resetdriver](#) (*module*), 121
[labgrid.driver.serialdigitaloutput](#) (*module*), 122
[labgrid.driver.serialdriver](#) (*module*), 122
[labgrid.driver.shelldriver](#) (*module*), 123
[labgrid.driver.sigrokdriver](#) (*module*), 125
[labgrid.driver.smallubootdriver](#) (*module*), 127
[labgrid.driver.sshdriver](#) (*module*), 128
[labgrid.driver.ubootdriver](#) (*module*), 128
[labgrid.driver.usbloader](#) (*module*), 130
[labgrid.driver.usbsdmuxdriver](#) (*module*), 132
[labgrid.driver.usbsdwireddriver](#) (*module*), 132
[labgrid.driver.usbstoragedriver](#) (*module*), 133
[labgrid.driver.usbtmc](#) (*module*), 103
[labgrid.driver.usbtmc.keysight_dsox2000](#) (*module*), 103
[labgrid.driver.usbtmc.tektronix_tds2000](#) (*module*), 104
[labgrid.driver.usbtmcdriver](#) (*module*), 134
[labgrid.driver.usbvideodriver](#) (*module*), 134
[labgrid.driver.xenadriver](#) (*module*), 135
[labgrid.environment](#) (*module*), 196
[labgrid.exceptions](#) (*module*), 197
[labgrid.factory](#) (*module*), 198
[labgrid.protocol](#) (*module*), 135

labgrid.protocol.bootstrapprotocol (*module*), 135

labgrid.protocol.commandprotocol (*module*), 136

labgrid.protocol.consoleprotocol (*module*), 136

labgrid.protocol.digitaloutputprotocol (*module*), 137

labgrid.protocol.filesystemprotocol (*module*), 137

labgrid.protocol.filetransferprotocol (*module*), 137

labgrid.protocol.infoprotocol (*module*), 138

labgrid.protocol.linuxbootprotocol (*module*), 138

labgrid.protocol.mmioprotocol (*module*), 138

labgrid.protocol.powerprotocol (*module*), 139

labgrid.protocol.resetprotocol (*module*), 139

labgrid.provider (*module*), 139

labgrid.provider.fileprovider (*module*), 139

labgrid.provider.mediafileprovider (*module*), 140

labgrid.pytestplugin (*module*), 140

labgrid.pytestplugin.fixtures (*module*), 140

labgrid.pytestplugin.hooks (*module*), 140

labgrid.pytestplugin.reporter (*module*), 141

labgrid.remote (*module*), 141

labgrid.remote.authenticator (*module*), 141

labgrid.remote.client (*module*), 141

labgrid.remote.common (*module*), 142

labgrid.remote.config (*module*), 145

labgrid.remote.coordinator (*module*), 145

labgrid.remote.exporter (*module*), 146

labgrid.remote.scheduler (*module*), 152

labgrid.resource (*module*), 152

labgrid.resource.base (*module*), 152

labgrid.resource.common (*module*), 154

labgrid.resource.docker (*module*), 156

labgrid.resource.ethernetport (*module*), 157

labgrid.resource.flashrom (*module*), 159

labgrid.resource.lxaiobus (*module*), 160

labgrid.resource.modbus (*module*), 161

labgrid.resource.networkservice (*module*), 161

labgrid.resource.onewireport (*module*), 161

labgrid.resource.power (*module*), 162

labgrid.resource.pyvisa (*module*), 162

labgrid.resource.remote (*module*), 163

labgrid.resource.serialport (*module*), 169

labgrid.resource.sigrok (*module*), 169

labgrid.resource.suggest (*module*), 170

labgrid.resource.udev (*module*), 170

labgrid.resource.xenamanager (*module*), 176

labgrid.resource.ykushpowerport (*module*), 177

labgrid.step (*module*), 199

labgrid.stepreporter (*module*), 200

labgrid.strategy (*module*), 177

labgrid.strategy.bareboxstrategy (*module*), 177

labgrid.strategy.common (*module*), 178

labgrid.strategy.dockerstrategy (*module*), 179

labgrid.strategy.graphstrategy (*module*), 179

labgrid.strategy.shellstrategy (*module*), 180

labgrid.strategy.ubootstrategy (*module*), 181

labgrid.target (*module*), 200

labgrid.util (*module*), 181

labgrid.util.agent (*module*), 182

labgrid.util.agents (*module*), 181

labgrid.util.agents.dummy (*module*), 181

labgrid.util.agents.sysfsgpio (*module*), 182

labgrid.util.agentwrapper (*module*), 183

labgrid.util.atomic (*module*), 184

labgrid.util.dict (*module*), 184

labgrid.util.exceptions (*module*), 184

labgrid.util.expect (*module*), 185

labgrid.util.helper (*module*), 185

labgrid.util.managedfile (*module*), 186

labgrid.util.marker (*module*), 187

labgrid.util.proxy (*module*), 187

labgrid.util.qmp (*module*), 187

labgrid.util.ssh (*module*), 188

labgrid.util.timeout (*module*), 190

labgrid.util.yaml (*module*), 191

LinuxBootProtocol (*class in labgrid.protocol.linuxbootprotocol*), 138

list () (*labgrid.provider.fileprovider.FileProvider method*), 140

list () (*labgrid.provider.mediafileprovider.MediaFileProvider method*), 140

list () (*labgrid.util.agent.Agent method*), 182

load () (*in module labgrid.util.yaml*), 191

load () (*labgrid.driver.flashromdriver.FlashromDriver method*), 112

- load() (*labgrid.driver.openocddriver.OpenOCDDriver method*), 115
- load() (*labgrid.driver.usbloader.IMXUSBDriver method*), 131
- load() (*labgrid.driver.usbloader.MXSUSBDriver method*), 130
- load() (*labgrid.driver.usbloader.RKUSBDriver method*), 131
- load() (*labgrid.driver.usbloader.UUUDriver method*), 131
- load() (*labgrid.protocol.bootstrapprotocol.BootstrapProtocol method*), 135
- load() (*labgrid.util.agent.Agent method*), 182
- load() (*labgrid.util.agentwrapper.AgentWrapper method*), 184
- Loader (*class in labgrid.util.yaml*), 191
- locked() (*in module labgrid.remote.coordinator*), 146
- log_callback() (*labgrid.util.helper.ProcessWrapper static method*), 185
- log_subprocess_kernel_stack() (*in module labgrid.remote.exporter*), 147
- loglevel (*labgrid.util.helper.ProcessWrapper attribute*), 185
- LXAIOBusNode (*class in labgrid.resource.lxaibus*), 160
- LXAIOBusNodeExport (*class in labgrid.remote.exporter*), 151
- LXAIOBusNodeManager (*class in labgrid.resource.lxaibus*), 160
- LXAIOBusPIO (*class in labgrid.resource.lxaibus*), 160
- LXAIOBusPIODriver (*class in labgrid.driver.lxaibusdriver*), 113
- manager_cls (*labgrid.resource.ethernetport.SNMPEthernetPort attribute*), 159
- manager_cls (*labgrid.resource.lxaibus.LXAIOBusNode attribute*), 160
- manager_cls (*labgrid.resource.remote.NetworkLXAIOBusNode attribute*), 168
- manager_cls (*labgrid.resource.remote.NetworkSysfsGPIO attribute*), 168
- manager_cls (*labgrid.resource.remote.RemotePlace attribute*), 163
- manager_cls (*labgrid.resource.remote.RemoteUSBResource attribute*), 163
- manager_cls (*labgrid.resource.udev.USBResource attribute*), 170
- ManualPowerDriver (*class in labgrid.driver.powerdriver*), 116
- measure() (*labgrid.driver.sigrokdriver.SigrokPowerDriver method*), 126
- MediaFileProvider (*class in labgrid.provider.mediafileprovider*), 140
- merge() (*labgrid.step.StepEvent method*), 199
- message (*labgrid.driver.serialdriver.SerialDriver attribute*), 122
- MethodProxy (*class in labgrid.util.agentwrapper*), 183
- MMIOProtocol (*class in labgrid.protocol.mmioprotocol*), 138
- ModbusCoilDriver (*class in labgrid.driver.modbusdriver*), 114
- ModbusTCPCoil (*class in labgrid.resource.modbus*), 161
- Mode (*class in labgrid.driver.usbstoragedriver*), 133
- model_id() (*labgrid.resource.udev.USBResource property*), 171
- ModuleProxy (*class in labgrid.util.agentwrapper*), 183
- monitor_command() (*labgrid.driver.qemudriver.QEMUDriver method*), 121
- MXSUSBDriver (*class in labgrid.driver.usbloader*), 130
- MXSUSBLoader (*class in labgrid.resource.udev*), 172
- ## M
- main() (*in module labgrid.autoinstall.main*), 101
- main() (*in module labgrid.remote.client*), 142
- main() (*in module labgrid.remote.exporter*), 152
- main() (*in module labgrid.resource.suggest*), 170
- main() (*in module labgrid.util.agent*), 182
- make_driver() (*labgrid.factory.TargetFactory method*), 198
- make_resource() (*labgrid.factory.TargetFactory method*), 198
- make_target() (*labgrid.factory.TargetFactory method*), 198
- ManagedFile (*class in labgrid.util.managedfile*), 186
- ManagedResource (*class in labgrid.resource.common*), 155
- Manager (*class in labgrid.autoinstall.main*), 101
- manager_cls (*labgrid.resource.common.ManagedResource attribute*), 155
- manager_cls (*labgrid.resource.docker.DockerDaemon attribute*), 156
- ## N
- name() (*labgrid.remote.coordinator.RemoteSession property*), 145
- NetworkAlteraUSBBlaster (*class in labgrid.resource.remote*), 165
- NetworkAndroidFastboot (*class in labgrid.resource.remote*), 164
- NetworkDeditecRelais8 (*class in labgrid.resource.remote*), 168
- NetworkFlashrom (*class in labgrid.resource.flashrom*), 159
- NetworkIMXUSBLoader (*class in labgrid.resource.remote*), 164

NetworkLXAIOPBusNode	(class in lab-grid.resource.remote), 168	notify()	(labgrid.stepreporter.StepReporter static method), 200
NetworkLXAIOPBusPIO	(class in lab-grid.resource.remote), 168	notify_console_match()	(lab-grid.protocol.consoleprotocol.ConsoleProtocol.Client method), 136
NetworkMXSUSBLoader	(class in lab-grid.resource.remote), 164	NoValidDriverError	184
NetworkPowerDriver	(class in lab-grid.driver.powerdriver), 117	O	
NetworkPowerPort	(class in lab-grid.resource.power), 162	oem_getenv()	(lab-grid.driver.fastbootdriver.AndroidFastbootDriver method), 111
NetworkResource	(class in lab-grid.resource.common), 154	off	(labgrid.strategy.bareboxstrategy.Status attribute), 177
NetworkRKUSBLoader	(class in lab-grid.resource.remote), 164	off	(labgrid.strategy.shellstrategy.Status attribute), 180
NetworkSerialPort	(class in lab-grid.resource.serialport), 169	off	(labgrid.strategy.ubootstrategy.Status attribute), 181
NetworkService	(class in lab-grid.resource.networkservice), 161	off()	(labgrid.driver.dockerdriver.DockerDriver method), 108
NetworkServiceExport	(class in lab-grid.remote.exporter), 151	off()	(labgrid.driver.fake.FakePowerDriver method), 111
NetworkSigrokUSBDevice	(class in lab-grid.resource.remote), 165	off()	(labgrid.driver.powerdriver.DigitalOutputPowerDriver method), 118
NetworkSigrokUSBSerialDevice	(class in lab-grid.resource.remote), 165	off()	(labgrid.driver.powerdriver.ExternalPowerDriver method), 117
NetworkSiSPMPowerPort	(class in lab-grid.resource.remote), 166	off()	(labgrid.driver.powerdriver.ManualPowerDriver method), 116
NetworkSysfsGPIO	(class in lab-grid.resource.remote), 168	off()	(labgrid.driver.powerdriver.NetworkPowerDriver method), 117
NetworkUSBMassStorage	(class in lab-grid.resource.remote), 166	off()	(labgrid.driver.powerdriver.PDUDaemonDriver method), 119
NetworkUSBPowerPort	(class in lab-grid.resource.remote), 167	off()	(labgrid.driver.powerdriver.SiSPMPowerDriver method), 116
NetworkUSBSDMuxDevice	(class in lab-grid.resource.remote), 166	off()	(labgrid.driver.powerdriver.USBPowerDriver method), 118
NetworkUSBSDWireDevice	(class in lab-grid.resource.remote), 166	off()	(labgrid.driver.powerdriver.YKUSHPowerDriver method), 118
NetworkUSBStorageDriver	(class in lab-grid.driver.usbstoragedriver), 133	off()	(labgrid.driver.qemudriver.QEMUDriver method), 120
NetworkUSBTMC	(class in labgrid.resource.remote), 167	off()	(labgrid.driver.sigrokdriver.SigrokPowerDriver method), 126
NetworkUSBVideo	(class in labgrid.resource.remote), 167	off()	(labgrid.protocol.powerprotocol.PowerProtocol method), 139
NoConfigFoundError	197	on()	(labgrid.driver.dockerdriver.DockerDriver method), 108
NoDriverFoundError	197	on()	(labgrid.driver.fake.FakePowerDriver method), 111
NoResourceFoundError	198	on()	(labgrid.driver.powerdriver.DigitalOutputPowerDriver method), 117
normalize_config()	(lab-grid.factory.TargetFactory static method), 198	on()	(labgrid.driver.powerdriver.ExternalPowerDriver method), 117
NoSupplierFoundError	197	on()	(labgrid.driver.powerdriver.ManualPowerDriver method), 116
notify()	(labgrid.consoleloggingreporter.ConsoleLoggingReporter static method), 196	on()	(labgrid.driver.powerdriver.NetworkPowerDriver method), 117
notify()	(labgrid.pytestplugin.reporter.StepReporter method), 141		
notify()	(labgrid.steps.steps method), 199		

<code>on()</code>	<code>(labgrid.driver.powerdriver.PDUDaemonDriver method), 119</code>	<code>120</code>	<code>on_activate()</code>	<code>(lab-grid.driver.serialdriver.SerialDriver method), 123</code>
<code>on()</code>	<code>(labgrid.driver.powerdriver.SiSPMPowerDriver method), 116</code>		<code>on_activate()</code>	<code>(lab-grid.driver.shelldriver.ShellDriver method), 123</code>
<code>on()</code>	<code>(labgrid.driver.powerdriver.USBPowerDriver method), 118</code>		<code>on_activate()</code>	<code>(lab-grid.driver.sigrokdriver.SigrokCommon method), 125</code>
<code>on()</code>	<code>(labgrid.driver.powerdriver.YKUSHPowerDriver method), 118</code>		<code>on_activate()</code>	<code>(labgrid.driver.sshdriver.SSHDriver method), 128</code>
<code>on()</code>	<code>(labgrid.driver.qemudriver.QEMUDriver method), 120</code>		<code>on_activate()</code>	<code>(lab-grid.driver.ubootdriver.UBootDriver method), 129</code>
<code>on()</code>	<code>(labgrid.driver.sigrokdriver.SigrokPowerDriver method), 126</code>		<code>on_activate()</code>	<code>(lab-grid.driver.usbloader.IMXUSBDriver method), 130</code>
<code>on()</code>	<code>(labgrid.protocol.powerprotocol.PowerProtocol method), 139</code>		<code>on_activate()</code>	<code>(lab-grid.driver.usbloader.MXSUSBDriver method), 130</code>
<code>on_activate()</code>	<code>(labgrid.binding.BindingMixin method), 192</code>		<code>on_activate()</code>	<code>(lab-grid.driver.usbloader.RKUSBDriver method), 131</code>
<code>on_activate()</code>	<code>(lab-grid.driver.bareboxdriver.BareboxDriver method), 104</code>		<code>on_activate()</code>	<code>(lab-grid.driver.usbloader.UUUDriver method), 131</code>
<code>on_activate()</code>	<code>(lab-grid.driver.deditecrelaisdriver.DeditecRelaisDriver method), 107</code>		<code>on_activate()</code>	<code>(lab-grid.driver.usbstoragedriver.USBStorageDriver method), 133</code>
<code>on_activate()</code>	<code>(lab-grid.driver.dockerdriver.DockerDriver method), 108</code>		<code>on_activate()</code>	<code>(lab-grid.driver.usbtmcdriver.USBTMCDriver method), 134</code>
<code>on_activate()</code>	<code>(lab-grid.driver.fastbootdriver.AndroidFastbootDriver method), 111</code>		<code>on_activate()</code>	<code>(lab-grid.driver.xenadriver.XenaDriver method), 135</code>
<code>on_activate()</code>	<code>(lab-grid.driver.flashromdriver.FlashromDriver method), 112</code>		<code>on_activate()</code>	<code>(labgrid.strategy.common.Strategy method), 178</code>
<code>on_activate()</code>	<code>(lab-grid.driver.gpiodriver.GpioDigitalOutputDriver method), 113</code>		<code>on_client_bound()</code>	<code>(labgrid.binding.BindingMixin method), 192</code>
<code>on_activate()</code>	<code>(lab-grid.driver.lxaibusdriver.LXAIOBusPIODriver method), 113</code>		<code>on_client_bound()</code>	<code>(lab-grid.resource.docker.DockerDaemon method), 157</code>
<code>on_activate()</code>	<code>(lab-grid.driver.modbusdriver.ModbusCoilDriver method), 114</code>		<code>on_client_bound()</code>	<code>(lab-grid.strategy.common.Strategy method), 178</code>
<code>on_activate()</code>	<code>(lab-grid.driver.onewiredriver.OneWirePIODriver method), 114</code>		<code>on_deactivate()</code>	<code>(labgrid.binding.BindingMixin method), 192</code>
<code>on_activate()</code>	<code>(lab-grid.driver.powerdriver.NetworkPowerDriver method), 117</code>		<code>on_deactivate()</code>	<code>(lab-grid.driver.bareboxdriver.BareboxDriver method), 104</code>
<code>on_activate()</code>	<code>(lab-grid.driver.powerdriver.PDUDaemonDriver method), 119</code>		<code>on_deactivate()</code>	<code>(lab-grid.driver.deditecrelaisdriver.DeditecRelaisDriver method), 107</code>
<code>on_activate()</code>	<code>(lab-grid.driver.pyvisadriver.PyVISADriver method), 119</code>			
<code>on_activate()</code>	<code>(lab-grid.driver.qemudriver.QEMUDriver method),</code>			

`on_deactivate()` (*lab-grid.driver.dockerdriver.DockerDriver* method), 108
`on_deactivate()` (*lab-grid.driver.externalconsoledriver.ExternalConsoleDriver* method), 109
`on_deactivate()` (*lab-grid.driver.fastbootdriver.AndroidFastbootDriver* method), 111
`on_deactivate()` (*lab-grid.driver.flashromdriver.FlashromDriver* method), 112
`on_deactivate()` (*lab-grid.driver.gpiodriver.GpioDigitalOutputDriver* method), 113
`on_deactivate()` (*lab-grid.driver.modbusdriver.ModbusCoilDriver* method), 114
`on_deactivate()` (*lab-grid.driver.onewiredriver.OneWirePIODriver* method), 115
`on_deactivate()` (*lab-grid.driver.pyvisadriver.PyVISADriver* method), 119
`on_deactivate()` (*lab-grid.driver.qemudriver.QEMUDriver* method), 120
`on_deactivate()` (*lab-grid.driver.serialdriver.SerialDriver* method), 123
`on_deactivate()` (*lab-grid.driver.shelldriver.ShellDriver* method), 123
`on_deactivate()` (*lab-grid.driver.sigrokdriver.SigrokCommon* method), 125
`on_deactivate()` (*lab-grid.driver.sshdriver.SSHDriver* method), 128
`on_deactivate()` (*lab-grid.driver.ubootdriver.UBootDriver* method), 129
`on_deactivate()` (*lab-grid.driver.usbloader.IMXUSBDriver* method), 131
`on_deactivate()` (*lab-grid.driver.usbloader.MXSUSBDriver* method), 130
`on_deactivate()` (*lab-grid.driver.usbloader.RKUSBDriver* method), 131
`on_deactivate()` (*lab-grid.driver.usbloader.UUUDriver* method), 131
`on_deactivate()` (*lab-grid.driver.usbstoragedriver.USBStorageDriver* method), 133
`on_deactivate()` (*lab-grid.driver.usbtmcdriver.USBTMCDriver* method), 134
`on_deactivate()` (*lab-grid.driver.xenadriver.XenaDriver* method), 135
`on_deactivate()` (*lab-grid.strategy.common.Strategy* method), 178
`on_poll()` (*labgrid.resource.docker.DockerDaemon* method), 157
`on_resource_added()` (*lab-grid.resource.common.ResourceManager* method), 155
`on_resource_added()` (*lab-grid.resource.docker.DockerManager* method), 156
`on_resource_added()` (*lab-grid.resource.ethernetport.EthernetPortManager* method), 158
`on_resource_added()` (*lab-grid.resource.remote.RemotePlaceManager* method), 163
`on_resource_added()` (*lab-grid.resource.udev.UdevManager* method), 170
`on_supplier_bound()` (*lab-grid.binding.BindingMixin* method), 192
`OneWirePIO` (class in *labgrid.resource.onewirereport*), 161
`OneWirePIODriver` (class in *lab-grid.driver.onewiredriver*), 114
`open()` (*labgrid.driver.externalconsoledriver.ExternalConsoleDriver* method), 109
`open()` (*labgrid.driver.fake.FakeConsoleDriver* method), 110
`open()` (*labgrid.driver.serialdriver.SerialDriver* method), 123
`OpenOCDDriver` (class in *lab-grid.driver.openocddriver*), 115

P

`params()` (*labgrid.remote.common.ResourceEntry* property), 142
`parent()` (*labgrid.resource.common.Resource* property), 154
`path()` (*labgrid.resource.udev.DeditecRelais8* property), 176
`path()` (*labgrid.resource.udev.SigrokUSBSerialDevice* property), 174

`path()` (*labgrid.resource.udev.USBMassStorage* property), 171
`path()` (*labgrid.resource.udev.USBResource* property), 171
`path()` (*labgrid.resource.udev.USBSDMuxDevice* property), 175
`path()` (*labgrid.resource.udev.USBSDWireDevice* property), 174
`path()` (*labgrid.resource.udev.USBTMC* property), 176
`path()` (*labgrid.resource.udev.USBVideo* property), 175
`PDUDaemonDriver` (class in *labgrid.driver.powerdriver*), 119
`PDUDaemonPort` (class in *labgrid.resource.power*), 162
`Place` (class in *labgrid.remote.common*), 143
`poll()` (*labgrid.remote.exporter.ResourceExport* method), 147
`poll()` (*labgrid.resource.common.ManagedResource* method), 155
`poll()` (*labgrid.resource.common.Resource* method), 154
`poll()` (*labgrid.resource.common.ResourceManager* method), 155
`poll()` (*labgrid.resource.docker.DockerManager* method), 156
`poll()` (*labgrid.resource.ethernetport.EthernetPortManager* method), 158
`poll()` (*labgrid.resource.lxaiobus.LXAIOBusNodeManager* method), 160
`poll()` (*labgrid.resource.remote.RemotePlaceManager* method), 163
`poll()` (*labgrid.resource.udev.UdevManager* method), 170
`poll()` (*labgrid.resource.udev.USBSDMuxDevice* method), 175
`poll()` (*labgrid.resource.udev.USBSDWireDevice* method), 174
`poll_until_success()` (*labgrid.driver.commandmixin.CommandMixin* method), 105
`poll_until_success()` (*labgrid.protocol.commandprotocol.CommandProtocol* method), 136
`pop()` (*labgrid.step.Steps* method), 199
`power_get()` (in module *labgrid.driver.power.apc*), 102
`power_get()` (in module *labgrid.driver.power.digipower*), 102
`power_get()` (in module *labgrid.driver.power.gude*), 102
`power_get()` (in module *labgrid.driver.power.gude24*), 102
`power_get()` (in module *labgrid.driver.power.gude8031*), 102
`power_get()` (in module *labgrid.driver.power.gude8316*), 103
`power_get()` (in module *labgrid.driver.power.netio*), 103
`power_get()` (in module *labgrid.driver.power.netio_kshell*), 103
`power_get()` (in module *labgrid.driver.power.sentry*), 103
`power_get()` (in module *labgrid.driver.power.simplerest*), 103
`power_set()` (in module *labgrid.driver.power.apc*), 102
`power_set()` (in module *labgrid.driver.power.digipower*), 102
`power_set()` (in module *labgrid.driver.power.gude*), 102
`power_set()` (in module *labgrid.driver.power.gude24*), 102
`power_set()` (in module *labgrid.driver.power.gude8031*), 102
`power_set()` (in module *labgrid.driver.power.gude8316*), 103
`power_set()` (in module *labgrid.driver.power.netio*), 103
`power_set()` (in module *labgrid.driver.power.netio_kshell*), 103
`power_set()` (in module *labgrid.driver.power.sentry*), 103
`power_set()` (in module *labgrid.driver.power.simplerest*), 103
`PowerProtocol` (class in *labgrid.protocol.powerprotocol*), 139
`PowerResetMixin` (class in *labgrid.driver.powerdriver*), 115
`print_callback()` (*labgrid.util.helper.ProcessWrapper* static method), 185
`priorities` (*labgrid.driver.powerdriver.PowerResetMixin* attribute), 115
`priorities` (*labgrid.driver.sshdriver.SSHDriver* attribute), 128
`ProcessWrapper` (class in *labgrid.util.helper*), 185
`PtxExpect` (class in *labgrid.util.expect*), 185
`push()` (*labgrid.step.Steps* method), 199
`put()` (*labgrid.driver.fake.FakeFileTransferDriver* method), 110
`put()` (*labgrid.driver.shelldriver.ShellDriver* method), 124
`put()` (*labgrid.driver.sshdriver.SSHDriver* method), 128
`put()` (*labgrid.protocol.filetransferprotocol.FileTransferProtocol* method), 137
`put_bytes()` (*labgrid.driver.shelldriver.ShellDriver*

method), 124
 put_file() (labgrid.util.ssh.SSHConnection method), 189
 put_ssh_key() (labgrid.driver.shelldriver.ShellDriver method), 124
 pytest_addoption() (in module labgrid.pytestplugin.fixtures), 140
 pytest_collection_modifyitems() (in module labgrid.pytestplugin.hooks), 140
 pytest_configure() (in module labgrid.pytestplugin.hooks), 140
 pytest_runtest_logreport() (labgrid.pytestplugin.reporter.StepReporter method), 141
 pytest_runtest_logstart() (labgrid.pytestplugin.reporter.StepReporter method), 141
 Python Enhancement Proposals
 PEP 8, 88
 PyVISADevice (class in labgrid.resource.pyvisa), 162
 PyVISADriver (class in labgrid.driver.pyvisadriver), 119

Q

QEMUDriver (class in labgrid.driver.qemudriver), 120
 QMPError, 188
 QMPMonitor (class in labgrid.util.qmp), 187
 QuartusHPSDriver (class in labgrid.driver.quartushpsdriver), 121
 query() (labgrid.driver.usbtmcdriver.USBTMCDriver method), 134

R

RawSerialPort (class in labgrid.resource.serialport), 169
 read() (labgrid.driver.consoleexpectmixin.ConsoleExpectMixin method), 106
 read() (labgrid.protocol.consoleprotocol.ConsoleProtocol method), 136
 read() (labgrid.protocol.filesystemprotocol.FileSystemProtocol method), 137
 read() (labgrid.protocol.mmioprotocol.MMIOProtocol method), 138
 read_attr() (labgrid.resource.udev.USBResource method), 171
 read_nonblocking() (labgrid.util.expect.PtxExpect method), 185
 refresh() (labgrid.remote.common.Reservation method), 144
 reg_driver() (labgrid.factory.TargetFactory method), 198
 reg_resource() (labgrid.factory.TargetFactory method), 198

register() (labgrid.util.agent.Agent method), 182
 register() (labgrid.util.helper.ProcessWrapper method), 185
 RegistrationError, 198
 release() (labgrid.remote.common.ResourceEntry method), 142
 release() (labgrid.remote.exporter.ResourceExport method), 147
 remaining() (labgrid.util.timeout.Timeout property), 191
 RemotePlace (class in labgrid.resource.remote), 163
 RemotePlaceManager (class in labgrid.resource.remote), 163
 RemoteSession (class in labgrid.remote.coordinator), 145
 RemoteUSBResource (class in labgrid.resource.remote), 163
 remove_port_forward() (labgrid.util.ssh.SSHConnection method), 189
 Reservation (class in labgrid.remote.common), 144
 ReservationState (class in labgrid.remote.common), 144
 reset() (labgrid.driver.bareboxdriver.BareboxDriver method), 104
 reset() (labgrid.driver.powerdriver.PowerResetMixin method), 115
 reset() (labgrid.driver.resetdriver.DigitalOutputResetDriver method), 121
 reset() (labgrid.driver.ubootdriver.UBootDriver method), 129
 reset() (labgrid.protocol.linuxbootprotocol.LinuxBootProtocol method), 138
 reset() (labgrid.protocol.resetprotocol.ResetProtocol method), 139
 ResetProtocol (class in labgrid.protocol.resetprotocol), 139
 resolve_conflicts() (labgrid.binding.BindingMixin method), 193
 resolve_conflicts() (labgrid.driver.consoleexpectmixin.ConsoleExpectMixin method), 107
 resolve_conflicts() (labgrid.strategy.common.Strategy method), 178
 resolve_path() (labgrid.config.Config method), 193
 resolve_path_str_or_list() (labgrid.config.Config method), 193
 resolve_templates() (in module labgrid.util.yaml), 191
 Resource (class in labgrid.resource.common), 154
 ResourceConfig (class in labgrid.remote.config), 145
 ResourceEntry (class in labgrid.remote.common), 142
 ResourceExport (class in labgrid.remote.exporter),

- 147
- ResourceImport (class in lab-grid.remote.coordinator), 146
- ResourceManager (class in lab-grid.resource.common), 155
- ResourceMatch (class in labgrid.remote.common), 142
- RKUSBDriver (class in labgrid.driver.usbloader), 131
- RKUSBLoader (class in labgrid.resource.udev), 172
- rsync () (labgrid.driver.sshdriver.SSHDriver method), 128
- run () (labgrid.autoinstall.main.Handler method), 101
- run () (labgrid.driver.bareboxdriver.BareboxDriver method), 104
- run () (labgrid.driver.fake.FakeCommandDriver method), 110
- run () (labgrid.driver.fastbootdriver.AndroidFastbootDriver method), 111
- run () (labgrid.driver.shelldriver.ShellDriver method), 124
- run () (labgrid.driver.sshdriver.SSHDriver method), 128
- run () (labgrid.driver.ubootdriver.UBootDriver method), 129
- run () (labgrid.protocol.commandprotocol.CommandProtocol method), 136
- run () (labgrid.resource.suggest.Suggester method), 170
- run () (labgrid.util.agent.Agent method), 182
- run () (labgrid.util.ssh.SSHConnection method), 188
- run_check () (labgrid.driver.commandmixin.CommandMixin method), 105
- run_check () (labgrid.driver.fake.FakeCommandDriver method), 110
- run_check () (labgrid.protocol.commandprotocol.CommandProtocol method), 136
- run_check () (labgrid.util.ssh.SSHConnection method), 188
- run_once () (labgrid.autoinstall.main.Handler method), 101
- run_script () (labgrid.driver.shelldriver.ShellDriver method), 124
- run_script_file () (lab-grid.driver.shelldriver.ShellDriver method), 125
- S**
- s2b () (in module labgrid.util.agent), 182
- s2b () (in module labgrid.util.agentwrapper), 183
- safe_dupfile () (in module lab-grid.pytestplugin.reporter), 141
- schedule () (in module labgrid.remote.scheduler), 152
- schedule_overlaps () (in module lab-grid.remote.scheduler), 152
- schedule_step () (in module lab-grid.remote.scheduler), 152
- scp () (labgrid.driver.sshdriver.SSHDriver method), 128
- select_caps () (lab-grid.driver.usbvideodriver.USBVideoDriver method), 134
- send () (labgrid.util.agent.Agent method), 182
- send () (labgrid.util.expect.PtxExpect method), 185
- sendcontrol () (lab-grid.driver.consoleexpectmixin.ConsoleExpectMixin method), 106
- sendcontrol () (lab-grid.protocol.consoleprotocol.ConsoleProtocol method), 136
- sendline () (labgrid.driver.consoleexpectmixin.ConsoleExpectMixin method), 106
- sendline () (labgrid.protocol.consoleprotocol.ConsoleProtocol method), 136
- SerialDriver (class in labgrid.driver.serialdriver), 122
- SerialPort (class in labgrid.resource.base), 152
- SerialPortDigitalOutputDriver (class in lab-grid.driver.serialdigitaloutput), 122
- SerialPortExport (class in lab-grid.remote.exporter), 147
- ServerError, 142
- set () (labgrid.driver.deditecrelaisdriver.DeditecRelaisDriver method), 107
- set () (labgrid.driver.filedigitaloutput.FileDigitalOutputDriver method), 112
- set () (labgrid.driver.gpiodriver.GpioDigitalOutputDriver method), 113
- set () (labgrid.driver.lxaiobusdriver.LXAIOPiODriver method), 113
- set () (labgrid.driver.modbusdriver.ModbusCoilDriver method), 114
- set () (labgrid.driver.onewiredriver.OneWirePiODriver method), 115
- set () (labgrid.driver.serialdigitaloutput.SerialPortDigitalOutputDriver method), 122
- set () (labgrid.protocol.digitaloutputprotocol.DigitalOutputProtocol method), 137
- set () (labgrid.util.agents.sysfsgpio.GpioDigitalOutput method), 182
- set_binding_map () (labgrid.target.Target method), 201
- set_current_limit () (lab-grid.driver.sigrokdriver.SigrokPowerDriver method), 126
- set_mode () (labgrid.driver.usbsdmuxdriver.USBSDMuxDriver method), 132
- set_mode () (labgrid.driver.usbsdwiredriver.USBSDWireDriver method), 132

- `set_option()` (*labgrid.config.Config* method), 194
 - `set_resource()` (*labgrid.remote.coordinator.ExporterSession* method), 146
 - `set_target_option()` (*labgrid.config.Config* method), 195
 - `set_voltage_target()` (*labgrid.driver.sigrokdriver.SigrokPowerDriver* method), 126
 - `shell` (*labgrid.strategy.bareboxstrategy.Status* attribute), 177
 - `shell` (*labgrid.strategy.shellstrategy.Status* attribute), 180
 - `shell` (*labgrid.strategy.ubootstrategy.Status* attribute), 181
 - `ShellDriver` (class in *labgrid.driver.shelldriver*), 123
 - `ShellStrategy` (class in *labgrid.strategy.shellstrategy*), 180
 - `show()` (*labgrid.remote.common.Place* method), 143
 - `show()` (*labgrid.remote.common.Reservation* method), 144
 - `SigrokCommon` (class in *labgrid.driver.sigrokdriver*), 125
 - `SigrokDevice` (class in *labgrid.resource.sigrok*), 169
 - `SigrokDriver` (class in *labgrid.driver.sigrokdriver*), 125
 - `SigrokPowerDriver` (class in *labgrid.driver.sigrokdriver*), 126
 - `SigrokUSBDevice` (class in *labgrid.resource.udev*), 173
 - `SigrokUSBSerialDevice` (class in *labgrid.resource.udev*), 174
 - `SiSPMPowerDriver` (class in *labgrid.driver.powerdriver*), 116
 - `SiSPMPowerPort` (class in *labgrid.resource.udev*), 175
 - `SiSPMPowerPortExport` (class in *labgrid.remote.exporter*), 149
 - `skip()` (*labgrid.step.Step* method), 200
 - `SmallUBootDriver` (class in *labgrid.driver.smallubootdriver*), 127
 - `SNMPEthernetPort` (class in *labgrid.resource.ethernetport*), 158
 - `SNMPSwitch` (class in *labgrid.resource.ethernetport*), 157
 - `SSHConnection` (class in *labgrid.util.ssh*), 188
 - `SSHDriver` (class in *labgrid.driver.sshdriver*), 128
 - `sshfs()` (*labgrid.driver.sshdriver.SSHDriver* method), 128
 - `start()` (*labgrid.autoinstall.main.Manager* method), 101
 - `start()` (*labgrid.consoleloggingreporter.ConsoleLoggingReporter* class method), 196
 - `start()` (*labgrid.remote.exporter.ResourceExport* method), 147
 - `start()` (*labgrid.step.Step* method), 200
 - `start()` (*labgrid.stepreporter.StepReporter* class method), 200
 - `start_session()` (in module *labgrid.remote.client*), 142
 - `StateError`, 191
 - `Status` (class in *labgrid.strategy.bareboxstrategy*), 177
 - `Status` (class in *labgrid.strategy.dockerstrategy*), 179
 - `Status` (class in *labgrid.strategy.shellstrategy*), 180
 - `Status` (class in *labgrid.strategy.ubootstrategy*), 181
 - `status()` (*labgrid.step.Step* property), 200
 - `Step` (class in *labgrid.step*), 199
 - `step()` (in module *labgrid.step*), 200
 - `StepEvent` (class in *labgrid.step*), 199
 - `StepReporter` (class in *labgrid.pytestplugin.reporter*), 141
 - `StepReporter` (class in *labgrid.stepreporter*), 200
 - `Steps` (class in *labgrid.step*), 199
 - `stop()` (*labgrid.consoleloggingreporter.ConsoleLoggingReporter* class method), 196
 - `stop()` (*labgrid.driver.sigrokdriver.SigrokDriver* method), 126
 - `stop()` (*labgrid.remote.exporter.ResourceExport* method), 147
 - `stop()` (*labgrid.step.Step* method), 200
 - `stop()` (*labgrid.stepreporter.StepReporter* class method), 200
 - `Strategy` (class in *labgrid.strategy.common*), 178
 - `strategy()` (in module *labgrid.pytestplugin.fixtures*), 140
 - `StrategyError`, 178
 - `stream()` (*labgrid.driver.usbvideodriver.USBVideoDriver* method), 134
 - `subscribe()` (*labgrid.step.Steps* method), 199
 - `suggest_callback()` (*labgrid.resource.suggest.Suggester* method), 170
 - `suggest_match()` (*labgrid.resource.udev.USBResource* method), 171
 - `Suggester` (class in *labgrid.resource.suggest*), 170
 - `sync_to_resource()` (*labgrid.util.managedfile.ManagedFile* method), 186
 - `SysfsGPIO` (class in *labgrid.resource.base*), 154
- ## T
- `TagSet` (class in *labgrid.remote.scheduler*), 152
 - `Target` (class in *labgrid.target*), 200
 - `target()` (in module *labgrid.pytestplugin.fixtures*), 140
 - `target_factory` (in module *labgrid.factory*), 199
 - `TargetFactory` (class in *labgrid.factory*), 198
 - `Timeout` (class in *labgrid.util.timeout*), 190

- touch() (*labgrid.remote.common.Place* method), 143
- transition() (*labgrid.strategy.bareboxstrategy.BareboxStrategy* method), 177
- transition() (*labgrid.strategy.common.Strategy* method), 178
- transition() (*labgrid.strategy.dockerstrategy.DockerStrategy* method), 179
- transition() (*labgrid.strategy.graphstrategy.GraphStrategy* method), 180
- transition() (*labgrid.strategy.shellstrategy.ShellStrategy* method), 180
- transition() (*labgrid.strategy.ubootstrategy.UBootStrategy* method), 181
- try_match() (*labgrid.resource.udev.USBResource* method), 171
- ## U
- uboot (*labgrid.strategy.ubootstrategy.Status* attribute), 181
- UBootDriver (class in *labgrid.driver.ubootdriver*), 128
- UBootStrategy (class in *labgrid.strategy.ubootstrategy*), 181
- UdevManager (class in *labgrid.resource.udev*), 170
- unknown (*labgrid.strategy.bareboxstrategy.Status* attribute), 177
- unknown (*labgrid.strategy.dockerstrategy.Status* attribute), 179
- unknown (*labgrid.strategy.shellstrategy.Status* attribute), 180
- unknown (*labgrid.strategy.ubootstrategy.Status* attribute), 181
- unregister() (*labgrid.util.helper.ProcessWrapper* method), 185
- unsubscribe() (*labgrid.step.Steps* method), 199
- UPD (*labgrid.remote.coordinator.Action* attribute), 145
- update() (*labgrid.remote.common.Place* method), 143
- update() (*labgrid.remote.common.ResourceEntry* method), 142
- update() (*labgrid.resource.ethernetport.SNMPSwitch* method), 157
- update() (*labgrid.resource.udev.USBEthernetInterface* method), 173
- update() (*labgrid.resource.udev.USBResource* method), 171
- update() (*labgrid.resource.udev.USBSerialPort* method), 171
- update_resources() (*labgrid.target.Target* method), 201
- USBDebounceRelaisExport (class in *labgrid.remote.exporter*), 150
- USBEthernetExport (class in *labgrid.remote.exporter*), 147
- USBEthernetInterface (class in *labgrid.resource.udev*), 173
- USBGenericExport (class in *labgrid.remote.exporter*), 148
- USBMassStorage (class in *labgrid.resource.udev*), 171
- USBPowerDriver (class in *labgrid.driver.powerdriver*), 118
- USBPowerPort (class in *labgrid.resource.udev*), 175
- USBPowerPortExport (class in *labgrid.remote.exporter*), 149
- USBResource (class in *labgrid.resource.udev*), 170
- USBSDMuxDevice (class in *labgrid.resource.udev*), 174
- USBSDMuxDriver (class in *labgrid.driver.usbsdmuxdriver*), 132
- USBSDMuxExport (class in *labgrid.remote.exporter*), 148
- USBSDWireDevice (class in *labgrid.resource.udev*), 174
- USBSDWireDriver (class in *labgrid.driver.usbsdwiredriver*), 132
- USBSDWireExport (class in *labgrid.remote.exporter*), 149
- USBSerialPort (class in *labgrid.resource.udev*), 171
- USBSigrokExport (class in *labgrid.remote.exporter*), 148
- USBStorageDriver (class in *labgrid.driver.usbstoragedriver*), 133
- USBTMC (class in *labgrid.resource.udev*), 176
- USBTMCDriver (class in *labgrid.driver.usbtmcdriver*), 134
- USBVideo (class in *labgrid.resource.udev*), 175
- USBVideoDriver (class in *labgrid.driver.usbvideodriver*), 134
- UserError, 141
- UUUDriver (class in *labgrid.driver.usbloder*), 131
- ## V
- vendor_id() (*labgrid.resource.udev.USBResource* property), 171
- ## W
- wait_for() (*labgrid.driver.commandmixin.CommandMixin* method), 105
- wait_for() (*labgrid.protocol.commandprotocol.CommandProtocol* method), 136
- waiting (*labgrid.remote.common.ReservationState* attribute), 144

`write()` (*labgrid.driver.consoleexpectmixin.ConsoleExpectMixin*
method), 106

`write()` (*labgrid.protocol.consoleprotocol.ConsoleProtocol*
method), 136

`write()` (*labgrid.protocol.filesystemprotocol.FileSystemProtocol*
method), 137

`write()` (*labgrid.protocol.mmioprotocol.MMIOProtocol*
method), 138

`write_image()` (*lab-*
grid.driver.usbstoragedriver.USBStorageDriver
method), 133

X

`XenaDriver` (*class in labgrid.driver.xenadriver*), 135

`XenaManager` (*class in lab-*
grid.resource.xenamanager), 176

Y

`yaml_constructors` (*labgrid.util.yaml.Loader* *at-*
tribute), 191

`yaml_representers` (*labgrid.util.yaml.Dumper* *at-*
tribute), 191

`YKUSHPowerDriver` (*class in lab-*
grid.driver.powerdriver), 118

`YKUSHPowerPort` (*class in lab-*
grid.resource.ykushpowerport), 177